

Navicat

Version 16

User Guide



Table of Contents

Chapter 1 - Introduction	11
About Navicat	11
Installation	14
Registration	14
Migration / Upgrade	15
End-User License Agreement	16
Chapter 2 - User Interface	22
Main Window	22
Navigation Pane	23
Object Pane	24
Information Pane	26
Chapter 3 - Collaboration	28
About Collaboration	28
Manage Cloud	28
Navicat Cloud	28
On-Prem Server	30
Push Synchronization	32
Cache and Local Copies	33
Projects	33
Work With Projects	33
Manage Members	34
Chapter 4 - Connection	36
About Connection	36
General Settings	37
RDBMS	37
MongoDB	39
Redis	40
Advanced Settings	41
Databases / Attached Databases Settings	44
SSL Settings	45
SSH Settings	47
HTTP Settings	48
Compatibility Settings	49
Connect with Different Profiles	50
Chapter 5 - Server Objects	51
About Server Objects	51
MySQL / MariaDB	51
Databases	51
Tables	51
Views	52

Procedures / Functions	53
Tablespaces	54
Events	54
Other Objects	54
Maintain Objects	54
Oracle	55
Schemas	55
Tables	55
Views	56
Materialized Views	57
Procedures / Functions	57
Packages	58
Recycle Bin	59
Other Objects	60
Maintain Objects	60
PostgreSQL	63
Databases & Schemas	63
Tables	63
Views	64
Materialized Views	65
Procedures / Functions	65
Types	66
Foreign Servers	67
Other Objects	67
Maintain Objects	67
Manage Extensions	68
SQL Server	68
Databases & Schemas	68
Tables	69
Views	70
Procedures / Functions	70
Other Objects	71
Maintain Objects	71
SQLite	72
Databases	72
Tables	73
Views	73
Other Objects	74
Maintain Objects	74
MongoDB	75
Databases	75
Collections	75

Views	76
Functions	76
Indexes	77
MapReduce	77
GridFS	77
Maintain Objects	78
Redis	79
Databases	79
Data	79
Chapter 6 - Data Viewer	80
About Data Viewer	80
RDBMS	80
RDBMS Data Viewer	80
Use Navigation Bar	80
Edit Records	81
Sort / Find / Replace Records	87
Filter Records	89
Manipulate Raw Data	89
Format Data View	90
View Field Comments	91
MongoDB	92
MongoDB Data Viewer	92
Use Navigation Bar	92
Grid View	93
Tree View	99
JSON View	101
Sort / Find / Replace Documents	101
Redis	104
Redis Data Viewer	104
Use Navigation Bar	104
Edit Keys	105
Sort Keys	105
Search Keys	106
Assistant Editors	106
Filter Wizard	107
Chapter 7 - Query	110
About Query	110
RDBMS	111
Query Editor	111
Query Builder (Available only in Non-Essentials Edition)	115
Query Parameters	121
Debug Oracle Query (Available only in Non-Essentials Edition)	121

Query Results	121
MongoDB	122
Query Editor	122
Find Builder (Available only in Non-Essentials Edition)	125
Aggregate Builder (Available only in Non-Essentials Edition)	126
Query Results	127
Redis	127
Query Editor	127
Query Results	131
Code Snippets (Available only in Non-Essentials Edition)	132
Chapter 8 - Model (Available only in Navicat Premium and Enterprise Edition)	134
About Model	134
Model Window	135
Physical Models	137
Create Physical Models	137
Add Databases / Schemas	138
Add Tables	138
Add Views	139
Add Foreign Keys	139
Logical Models	140
Create Logical Models	140
Add Entities	140
Add Relations	141
Conceptual Models	141
Create Conceptual Models	141
Add Entities	142
Add Relations	142
Diagram Layout	143
Work with Diagram Canvas	143
Add Labels	144
Add Notes	144
Add Images	145
Add Shapes	145
Add Layers	146
Reverse Engineering	147
Forward Engineering	147
Synchronize to Database	147
Export SQL	151
Model Conversion	153
Print & Export Model	153
Model Hints and Tips	153
Chapter 9 - Debugger (Available only in Non-Essentials Edition)	156

About Debugger	156
Oracle PL/SQL Debugger	156
PostgreSQL PL/pgSQL Debugger	157
Chapter 10 - Pub/Sub (Available only in Non-Essentials Edition)	160
About Pub/Sub	160
Pub/Sub Window	160
Subscribe Channels	161
Channel Colorings	162
Chapter 11 - Data Migration Tools	163
About Data Migration Tools	163
Import Wizard	163
About Import Wizard	163
Choose File Format	163
Choose Source File	163
Choose Delimiter	164
Choose Additional Options	166
Choose Target Table / Collection	166
Adjust Field Structures and Map Fields	167
Choose Import Mode	168
Save and Start Import	169
Export Wizard	169
About Export Wizard	169
Choose File Format	169
Choose Saving Path	169
Choose Columns / Fields for Export	171
Choose Additional Options	171
Save and Start Export	173
Data Transfer (Available only in Non-Essentials Edition)	173
About Data Transfer	173
Choose Connections & Advanced Options (Step 1)	173
Choose Objects & Transfer Mode (Step 2)	177
Confirm & Start Data Transfer (Step 3)	178
Data Synchronization (Available only in Non-Essentials Edition)	179
About Data Synchronization	179
Choose Connections & Comparing Options (Step 1)	179
Choose Table / Collection Mapping (Step 2)	180
View Data Comparison Results (Step 3)	180
Edit & Execute Selected Scripts (Step 4)	181
Structure Synchronization (Available only in Non-Essentials Edition)	182
About Structure Synchronization	182
Choose Connections & Comparing Options (Step 1)	182
View Structure Comparison Results (Step 2)	184

Edit & Execute Selected Scripts (Step 3)	186
Dump & Execute SQL / Script File	186
Execute Command File	187
MongoImport & MongoExport	188
About MongoImport & MongoExport	188
MongoImport	188
MongoExport	188
Chapter 12 - Data Generation (Available only in Non-Essentials Edition)	189
About Data Generation	189
Choose Target Connection (Step 1)	189
Choose Objects & Column Properties (Step 2)	190
Use Generator (Step 2.1)	191
Number Generator	191
Date / Time / DateTime Generator	191
Sequence Generator	192
Enum Generator	192
Text Generator	192
Image/Binary Generator	192
Foreign Key Generator	193
UUID Generator	193
Regular Expression Generator	193
Name Generator	195
Gender Generator	195
Title Generator	195
Marital Status Generator	195
Phone Number Generator	196
Email Generator	196
Job Title Generator	196
Social Network ID Generator	196
Payment Method Generator	197
Credit Card Type Generator	197
Credit Card Number Generator	197
Credit Card Date Generator	197
Company Name Generator	198
Department Generator	198
Industry Generator	198
Address Generator	198
City Generator	199
Region Generator	199
Product Name Generator	199
Product Category Generator	199
Color Generator	200

Size Generator	200
Weight Unit Generator	200
Barcode Generator	200
SKU Generator	201
IP Address Generator	201
MAC Address Generator	201
File Path Generator	201
File Name Generator	202
File Extension Generator	202
URL Generator	202
Hostname Generator	202
Preview Data & Start Generation (Step 3)	203
Chapter 13 - Charts (Available only in Navicat Premium and Enterprise Edition)	204
About Charts	204
Workspace	205
Data Source	206
About Data Source	206
Create Data Source	207
Modify Data Source Connections	208
Filter / Sort / Project Data	210
Add Custom Fields	212
Chart	213
About Chart	213
Build Chart	214
Filter / Sort Data	216
Apply Aggregate Function	217
Add Range	218
Set Value Operation	219
Chart Types	219
About Chart Types	219
Bar Chart	220
Line / Area Chart	223
Bar and Line Chart	226
Waterfall Chart	229
Tornado Chart	231
Pie / Donut Chart	234
Scatter Chart	235
Heatmap	238
Treemap	240
Value	241
Trend	242
KPI	243

Gauge	244
Table	246
Pivot Table	247
Control	249
DateTime Formats	250
Dashboard	251
About Dashboard	251
Build Dashboard	252
Add Pages	253
Add Charts	253
Add Text Labels	254
Add Images	254
Add Shapes	255
Arrange Objects	256
Present Dashboard	257
Print & Export Dashboard	257
Switch Theme	257
Chapter 14 - Automation (Available only in Non-Essentials Edition)	259
About Automation	259
Create Batch Job (Step 1)	259
Schedule Batch Job (Step 2)	261
Chapter 15 - Backup & Restore	263
About Backup & Restore	263
MySQL / PostgreSQL / SQLite / MariaDB (Available only in Non-Essentials Edition)	263
About Built-in Backup & Restore Tool	263
Backup	263
Restore	264
Extract SQL	266
Oracle Data Pump (Available only in Non-Essentials Edition)	267
About Oracle Data Pump	267
Oracle Data Pump Export	267
Oracle Data Pump Import	270
SQL Server Backup & Restore (Available only in Non-Essentials Edition)	273
About SQL Server Backup & Restore	273
SQL Server Backup	273
SQL Server Restore	276
MongoDump & MongoRestore	277
About MongoDump & MongoRestore	277
MongoDump	277
MongoRestore	277
Redis (Available only in Non-Essentials Edition)	278
About Built-in Backup & Restore Tool	278

Backup	278
Restore	279
Extract Command	280
Chapter 16 - Server Security	282
About Server Security	282
MySQL / MariaDB User & Role Management	282
User Designer	282
Role Designer	283
Oracle User & Role Management	284
User Designer	284
Role Designer	285
Maintain User	286
PostgreSQL User, Group & Role Management	287
User Designer	287
Group Designer	288
Role Designer	288
SQL Server Login, Role & user Management	290
Login Designer	290
Server Role Designer	292
Database User Designer	292
Database Role Designer	293
Application Role Designer	294
SQLite User Management	295
MongoDB User & Role Management	296
User Designer	296
Role Designer	297
Redis User Management	298
Privilege Manager	299
Chapter 17 - Other Advanced Tools	300
Server Monitor (Available only in Non-Essentials Edition)	300
Schema Analysis (Available only in Non-Essentials Edition)	300
Command Monitor (Available only in Non-Essentials Edition)	301
Virtual Grouping (Available only in Non-Essentials Edition)	302
Connection Colorings	302
Find in Database/Schema (Available only in Non-Essentials Edition)	303
Print Structure (Available only in Non-Essentials Edition)	303
Console	304
Favorites (Available only in Non-Essentials Edition)	304
Dark Theme	305
Search Filter	305
Chapter 18 - Configurations	307
Options Settings	307

General	307
Tabs	308
Code Completion (Available only in Non-Essentials Edition)	309
Editor	309
Records	310
Auto Recovery	312
File Locations	312
Connectivity	314
Environment	314
Advanced	315
Chapter 19 - Hot Keys	317
Navicat Hot Keys	317
Chapter 20 - Trace Logs	321
Log Files	321

Chapter 1 - Introduction

About Navicat

Navicat is a multi-connections Database Administration tool allowing you to connect to MySQL, MariaDB, MongoDB, SQL Server, Oracle, PostgreSQL, SQLite, and/or Redis databases, making database administration to multiple kinds of database so easy. It can also manage cloud databases such as Amazon Redshift, Amazon RDS, Alibaba Cloud. Features in Navicat are sophisticated enough to provide professional developers for all their specific needs, yet easy to learn for users who are new to database server. With its well-designed Graphical User Interface(GUI), Navicat lets you quickly and easily create, organize, access and share information in a secure and easy way.

Navicat is available on three platforms - Microsoft Windows, macOS and Linux. It can connect to local/remote servers, providing several utility tools such as Cloud Collaboration, Data Modeling, Data Transfer, Data/Structure Synchronization, Import/Export, Backup/Restore, Charts, Data Generation and Automation.

For details, visit our website: <https://www.navicat.com>

System Requirements

Windows

- Microsoft Windows 7, Windows 8, Windows 8.1, Windows 10, Windows 11, Server 2012, Server 2016, Server 2019, Server 2022

macOS

- macOS 10.14 Mojave, macOS 10.15 Catalina, macOS 11 Big Sur, macOS 12 Monterey, macOS 13 Ventura

Linux

- Debian 9, Debian 10, Debian 11, Ubuntu 18.04, Ubuntu 20.04, Ubuntu 22.04, Fedora 33, Fedora 34, Fedora 35, Linux Mint 19, Linux Mint 20, Linux Mint 21, Deepin 20, KylinOS Desktop 10

Supported On-Premises Databases

- MySQL 3.23 or later, Drizzle, OurDelta, Percona Server
- PostgreSQL 7.3 or later
- Oracle 8i or later
- SQLite 2 and 3
- SQL Server 2000 or later
- MariaDB 5.1 or later
- MongoDB 3.0 to 6.0

- Redis 2.8 or later
- OceanBase Community and Enterprise 3.1.0 or later (Enterprise Oracle Mode is not available in macOS Edition)

Supported Cloud Databases

Amazon AWS

- Amazon Redshift
- Amazon Aurora for MySQL
- Amazon Aurora for PostgreSQL
- Amazon RDS for MySQL
- Amazon RDS for PostgreSQL
- Amazon RDS for Oracle
- Amazon RDS for SQL Server
- Amazon RDS for MariaDB
- Amazon DocumentDB
- Amazon ElastiCache for Redis

Google Cloud

- Google Cloud SQL for MySQL
- Google Cloud SQL for PostgreSQL
- Google Cloud SQL for SQL Server
- Google Memorystore (Redis)

Oracle Cloud

- Oracle Database Cloud Service
- Oracle MySQL Cloud Service

Microsoft Azure

- Microsoft Azure SQL Database
- Microsoft Azure Database for MySQL

- Microsoft Azure Database for PostgreSQL
- Microsoft Azure Database for MariaDB
- Microsoft Azure Cache for Redis

MongoDB Cloud Services

- MongoDB Atlas

Redis Enterprise Cloud

- Redis Enterprise Cloud

Alibaba Cloud

- Alibaba Cloud ApsaraDB RDS for MySQL
- Alibaba Cloud ApsaraDB RDS for PostgreSQL
- Alibaba Cloud ApsaraDB RDS for SQL Server
- Alibaba Cloud ApsaraDB for MongoDB
- Alibaba Cloud ApsaraDB for Redis
- Alibaba Cloud ApsaraDB for OceanBase (MySQL Mode)
- Alibaba Cloud ApsaraDB for OceanBase (Oracle Mode)

Tencent Cloud

- Tencent Cloud TencentDB for MySQL
- Tencent Cloud TencentDB for PostgreSQL
- Tencent Cloud TencentDB for SQL Server
- Tencent Cloud TencentDB for MariaDB
- Tencent Cloud TencentDB for MongoDB
- Tencent Cloud TencentDB for Redis

Huawei Cloud

- Huawei Cloud RDS for MySQL
- Huawei Cloud RDS for PostgreSQL
- Huawei Cloud RDS for SQL Server

- Huawei Cloud Document Database Service
- Huawei Cloud Distributed Cache Service for Redis
- Huawei Cloud GaussDB Centralized

Installation

We strongly suggest that you shut down any opened applications. This will help ensure a smooth installation.

Installation for Download Version

1. Download Navicat Windows version.
2. Open the **.exe** file.
3. Click **Next** at the Welcome Screen.
4. Read the License Agreement. Accept it and click **Next**.
5. Accept the location of the program icons by clicking **Next**. If you wish to change the destination of the folder, click **Browse**.
6. Follow the remaining steps.

Installation for CD Version

1. Load the Navicat CD Installation disk into the CD-ROM drive.
2. Open the **.exe** file.
3. Click **Next** at the Welcome Screen.
4. Read the License Agreement. Accept it and click **Next**.
5. Accept the location of the program icons by clicking **Next**. If you wish to change the destination of the folder, click **Browse**.
6. Follow the remaining steps.

Registration

When the trial period is finished, Navicat requires a license key or a subscription plan to continue using the features.

Note: Perpetual License and Subscription Plan cannot be used at the same Navicat. Before changing the registration method, you need to deactivate the license key or sign out your Navicat ID.

Perpetual License

If you have purchased a perpetual license, you will receive a license key for activating Navicat.

In the **Perpetual License** section, paste your license key (16 digits) and click the **Activate** button. Navicat contacts our licensing server to activate the license key. If the activation process is successful, the license key details are displayed.

Manual Activation

Manual activation is available when your computer does not have an internet connection. You will need another computer with an internet connection to complete this activation process.

1. If the online activation is failed, click **Manual Activation**.
2. Copy the Request Code in the **Copy the Request Code Here:** box.
3. Open web browser on a computer with an internet connection and then go to https://customer.navicat.com/manual_activate.php.
4. Paste/Enter the Request Code into the left box.
5. Click **Get Activation Code**.
6. Copy the generated Activation Code in the right box.
7. Go back to the computer where you are activating Navicat.
8. Paste the Activation Code into the **Paste the Activation Code Here:** box.
9. Click **Activate**.

Subscription Plan

If you have subscribed a plan, you can sign in your Navicat ID to use Navicat during the subscription term.

Note: Navicat ID is the Email address that you used to subscribe the plan.

In the **Subscription** section, provide your **Navicat ID** and **Password**. After signed in, the subscription plan details are displayed.

Navicat contacts our licensing server once per hour to auto reload the plan by default. If you have updated your plan in the portal site, you can use the **Reload Plan** button to force reloading the new plan.

Note: Each Navicat ID can connect to only one Navicat. If you sign in your Navicat ID in another Navicat, you will be signed out from the current Navicat.

Migration / Upgrade

Migrate Navicat to a new computer

1. In Navicat, choose **File -> Export Connections**. The exported file (.ncx) contains all your connection settings.

2. Backup the exported file (.ncx).
3. In Navicat, choose **Help -> Registration**.
4. [Perpetual License] Click **Deactivate** to online deactivate the license key.
5. [Subscription Plan] Click **Sign Out** to sign out your Navicat ID.
6. Uninstall Navicat from the existing computer.
7. Re-install Navicat in the new computer.
8. Open Navicat and choose **File -> Import Connections** in the new computer to import the connection settings (.ncx).

When a new connection is being established, Navicat will create a subfolder under [Settings Location](#). Most files are stored within this subfolder. To look for the path, right-click the connection and select **Edit Connection -> Advanced -> Settings Location**.

Moreover, all your saved profiles are stored under [profiles](#). To look for the path, choose **Tools -> Options -> File Locations -> Profiles Location**.

Upgrade Navicat

If you want to upgrade an installed copy of Navicat to the latest release, please choose **Help -> Check For Updates** to start the Updater. It will automatically check your installed version. If there is a new version, simply follow the steps in the Updater to upgrade your Navicat. It will replace your previous Navicat and your current settings will remain unchanged.

Or, you can submit your registered email address on the [Customer Center](#) to download the latest version installer.

End-User License Agreement

Note: For the License Agreement of Navicat Cloud service, please click [here](#).

IMPORTANT: THIS SOFTWARE END USER LICENSE AGREEMENT ("EULA") IS A LEGAL AGREEMENT BETWEEN YOU (EITHER AN INDIVIDUAL OR, IF PURCHASED OR OTHERWISE ACQUIRED BY OR FOR AN ENTITY, AN ENTITY) AND PREMIUMSOFT CYBERTECH LTD..READ IT CAREFULLY BEFORE COMPLETING THE INSTALLATION PROCESS AND USING THE SOFTWARE. IT PROVIDES A LICENSE TO USE THE SOFTWARE AND CONTAINS WARRANTY INFORMATION AND LIABILITY DISCLAIMERS. BY INSTALLING AND USING THE SOFTWARE, YOU ARE CONFIRMING YOUR ACCEPTANCE OF THE SOFTWARE AND AGREEING TO BECOME BOUND BY THE TERMS OF THIS AGREEMENT. IF YOU DO NOT AGREE TO BE BOUND BY THESE TERMS, THEN DO NOT INSTALL THE SOFTWARE AND RETURN THE SOFTWARE TO YOUR PLACE OF PURCHASE. THIS EULA SHALL APPLY ONLY TO THE SOFTWARE SUPPLIED BY PREMIUMSOFT CYBERTECH LTD. HEREWITH REGARDLESS OF WHETHER OTHER SOFTWARE IS REFERRED TO OR DESCRIBED HEREIN.

1. Definitions

- a. "Non-commercial Version" means a version of the Software, so identified, for use by i) the individual who is a natural person and not a corporation, company, partnership or association or other entity or organization (ii) the individual who is a student, faculty or staff member at an educational institution, and (iii) staff of a non-profit organization or charity organization only. For purposes of this definition, "educational institution" means a public or private school, college, university and other post secondary educational establishment. A non-profit organization is an organization whose primary objective is to support an issue or matter of private interest or public concern for non-commercial purposes.
- b. "Not For Resale (NFR) Version" means a version, so identified, of the Software to be used to review and evaluate the Software, only.
- c. "PremiumSoft" means PREMIUMSOFT CYBERTECH LTD. and its licensors, if any.
- d. "Software" means only the PremiumSoft software program(s) and third party software programs, in each case, supplied by PremiumSoft herewith, and corresponding documentation, associated media, printed materials, and online or electronic documentation.
- e. "Unregistered version", "Trial version" or "Demo version" means an unregistered copy of the SOFTWARE ("UNREGISTERED SOFTWARE") which may be used by the USER for evaluation purposes for a period of fourteen (14) days following the initial installation of the UNREGISTERED SOFTWARE. At the end of the trial period ("TRIAL PERIOD"), the USER must either register the SOFTWARE or remove it from his system. The UNREGISTERED SOFTWARE may be freely copied and distributed to other users for their evaluation.
- f. "Navicat Essentials" means a version of the Software, so identified, to be used for commercial purpose.

2. License Grants

The licenses granted in this Section 2 are subject to the terms and conditions set forth in this EULA:

- a. Subject to Section 2(b), you may install and use the Software on a single computer; OR install and store the Software on a storage device, such as a network server, used only to install the Software on your other computers over an internal network, provided you have a license for each separate computer on which the Software is installed and run. Except as otherwise provided in Section 2(b), a license for the Software may not be shared, installed or used concurrently on different computers.
- b. In addition to the single copy of the Software permitted in Section 2(a), the primary user of the computer on which the Software is installed may make a second copy of the Software and install it on either a portable computer or a computer located at his or her home for his or her exclusive use, provided that:
 - A. the second copy of the Software on the portable or home computer (i) is not used at the same time as the copy of the Software on the primary computer and (ii) is used by the primary user solely as allowed for such version or edition (such as for educational use only),
 - B. the second copy of the Software is not installed or used after the time such user is no longer the primary user of the primary computer on which the Software is installed.
- c. In the event the Software is distributed along with other PremiumSoft software products as part of a suite of products (collectively, the "Studio"), the license of the Studio is licensed as a single product and none of the products in the Studio, including the Software, may be separated for installation or use on more than one computer.

- d. You may make one copy of the Software in machine-readable form solely for backup purposes. You must reproduce on any such copy all copyright notices and any other proprietary legends on the original copy of the Software. You may not sell or transfer any copy of the Software made for backup purposes.
- e. You agree that PremiumSoft may audit your use of the Software for compliance with these terms at any time, upon reasonable notice. In the event that such audit reveals any use of the Software by you other than in full compliance with the terms of this Agreement, you shall reimburse PremiumSoft for all reasonable expenses related to such audit in addition to any other liabilities you may incur as a result of such non-compliance.
- f. Your license rights under this EULA are non-exclusive.

3. License Restrictions

- a. Other than as set forth in Section 2, you may not make or distribute copies of the Software, or electronically transfer the Software from one computer to another or over a network.
- b. You may not alter, merge, modify, adapt or translate the Software, or decompile, reverse engineer, disassemble, or otherwise reduce the Software to a human-perceivable form.
- c. Unless otherwise provided herein, you may not rent, lease, or sublicense the Software.
- d. Other than with respect to a Trial / Demo Version, Non-commercial Lite Version or a Not For Resale Version of the Software, you may permanently transfer all of your rights under this EULA only as part of a sale or transfer, provided you retain no copies, you transfer all of the Software (including all component parts, the media and printed materials, any upgrades, this EULA, the serial numbers, and, if applicable, all other software products provided together with the Software), and the recipient agrees to the terms of this EULA. If the Software is an upgrade, any transfer must include all prior versions of the Software from which you are upgrading. If the copy of the Software is licensed as part of the whole Studio (as defined above), the Software shall be transferred only with and as part of the sale or transfer of the whole Studio, and not separately. You may retain no copies of the Software. You may not sell or transfer any Trial / Demo Version, Non-commercial Lite Version or Not For Resale Version of the Software.
- e. Unless otherwise provided herein, you may not modify the Software or create derivative works based upon the Software.
- f. Non-commercial Versions of the Software may not be used for, or distributed to any party for, any commercial purpose.
- g. Unless otherwise provided herein, you shall not
 - A. in the aggregate, install or use more than one copy of the Trial / Demo Version and Non-commercial Lite Version of the Software,
 - B. download the Trial / Demo Version and Non-commercial Lite Version of the Software under more than one username,
 - C. alter the contents of a hard drive or computer system to enable the use of the Trial / Demo Version of the Software for an aggregate period in excess of the trial period for one license to such Trial / Demo Version,
 - D. disclose the results of software performance benchmarks obtained using the Trial / Demo Version or Non-commercial Lite Version to any third party without PremiumSoft prior written consent, or
 - E. use the Trial / Demo Version of the Software for a purpose other than the sole purpose of determining whether to purchase a license to a commercial or education version of the software; provided, however,

notwithstanding the foregoing, you are strictly prohibited from installing or using the Trial / Demo Version or Non-commercial Lite Version of the Software for any commercial training purpose.

- h. You may only use the Not for Resale Version of the Software to review and evaluate the Software.
- i. You may receive the Software in more than one medium but you shall only install or use one medium. Regardless of the number of media you receive, you may use only the medium that is appropriate for the server or computer on which the Software is to be installed.
- j. You may receive the Software in more than one platform but you shall only install or use one platform.
- k. You shall not use the Software to develop any application having the same primary function as the Software.
- l. In the event that you fail to comply with this EULA, PremiumSoft may terminate the license and you must destroy all copies of the Software (with all other rights of both parties and all other provisions of this EULA surviving any such termination).
- m. This program may include Oracle Instant Client (OCI). You agree that you shall
 - 1. not use of the Oracle Instant Client to the business operations;
 - 2. not assign, give, or transfer the Oracle Instant Client or an interest in them to another individual or entity;
 - a. make the Programs available in any manner to any third party for use in the third party's business operations; and
 - b. title to the Programs from passing to the end user or any other party;
 - 3. not reverse engineer, disassemble or decompilation the Oracle Instant Client and duplicate the Programs except for a sufficient number of copies of each Program for your licensed use and one copy of each Program media;
 - 4. discontinue use and destroy or return to all copies of the Oracle Instant Client and documentation after termination of the Agreement;
 - 5. not publish any results of benchmark tests run on the Programs;
 - 6. comply fully with all relevant export laws and regulations of the United States and other applicable export and import laws to assure that neither the Oracle Instant Client, nor any direct product thereof, are exported, directly or indirectly, in violation of applicable laws;
 - 7. allow PremiumSoft to audit your use of the Oracle Instant Client;

4. Upgrades

If this copy of the Software is an upgrade from an earlier version of the Software, it is provided to you on a license exchange basis. You agree by your installation and use of such copy of the Software to voluntarily terminate your earlier EULA and that you will not continue to use the earlier version of the Software or transfer it to another person or entity unless such transfer is pursuant to Section 3.

5. Ownership

The foregoing license gives you limited license to use the Software. PremiumSoft and its suppliers retain all rights, title and interest, including all copyright and intellectual property rights, in and to, the Software (as an independent work and as an underlying work serving as a basis for any application you may develop), and all copies thereof. All rights not specifically granted in this EULA, including Federal and International Copyrights, are reserved by PremiumSoft and its suppliers.

6. LIMITED WARRANTY AND DISCLAIMER

- a. Except with respect to Trial / Demo Version, Non-commercial Lite Version and Not For Resale Version of the Software, PremiumSoft warrants that, for a period of thirty (30) days from the date of delivery (as evidenced by a copy of your receipt): the physical media on which the Software is furnished will be free from defects in materials and workmanship under normal use. The Software is provided "as is". PremiumSoft makes no warranties, express or implied, arising from course of dealing or usage of trade, or statutory, as to any matter whatsoever.
- b. PremiumSoft provides no remedies or warranties, whether express or implied, for Trial / Demo version, Non-commercial Lite version and the Not for Resale version of the Software. Trial / Demo version, Non-commercial Lite version and the Not for Resale version of the Software are provided "as is".
- c. Except as set Forth in the foregoing limited warranty with respect to software other than Trial/ Demo version, Non-commercial Lite version and Not for Resale version, PremiumSoft and its suppliers disclaim all other warranties and representations, whether express, implied, or otherwise, including the warranties of merchantability or fitness for a particular purpose. Also, there is no warranty of non-infringement and title or quiet enjoyment. PremiumSoft does not warrant that the Software is error-free or will operate without interruption. The Software is not designed, intended or licensed for use in hazardous environments requiring fail-safe controls, including without limitation, the design, construction, maintenance or operation of nuclear facilities, aircraft navigation or communication systems, air traffic control, and life support or weapons systems. PremiumSoft specifically disclaims any express or implied warranty of fitness for such purposes.
- d. If applicable law requires any warranties with respect to the Software, all such warranties are limited in duration to thirty (30) days from the date of delivery.
- e. No oral or written information or advice given by PremiumSoft, its dealers, distributors, agents or employees shall create a warranty or in any way increase the scope of ANY warranty PROVIDED HEREIN.

7. LIMITATION OF LIABILITY

(a) Neither PremiumSoft nor its suppliers shall be liable to you or any third party for any indirect, special, incidental, punitive or consequential damages (including, but not limited to, damages for the inability to use equipment or access data, loss of business, loss of profits, business interruption or the like), arising out of the use of, or inability to use, the Software and based on any theory of liability including breach of contract, breach of warranty, tort (including negligence), product liability or otherwise, even if PremiumSoft or its representatives have been advised of the possibility of such damages.

8. Third Party Software

The Software may contain third party software which requires notices and/or additional terms and conditions. By accepting this EULA, you are also accepting the additional terms and conditions of the third party software.

9. General

No PremiumSoft dealer, agent or employee is authorized to make any amendment to this EULA.

This EULA contains the complete agreement between the parties with respect to the subject matter hereof, and supersedes all prior or contemporaneous agreements or understandings, whether oral or written. You agree that any varying or additional terms contained in any purchase order or other written notification or document issued by you in relation to the Software licensed hereunder shall be of no effect. The failure or delay of PremiumSoft to exercise any of its rights under this EULA or upon any breach of this EULA shall not be deemed a waiver of those rights or of the breach.

If any provision of this EULA shall be held by a court of competent jurisdiction to be contrary to law, that provision will be enforced to the maximum extent permissible, and the remaining provisions of this EULA will remain in full force and effect.

10. Basis of Bargain

The Limited Warranty and Disclaimer and Limited Liability set forth above are fundamental elements of the basis of the agreement between PremiumSoft and you. PremiumSoft would not be able to provide the Software on an economic basis without such limitations. Such Limited Warranty and Disclaimer and Limited Liability inure to the benefit of PremiumSoft's licensors.

11. Term

By downloading and/or installing this SOFTWARE, the Licensor agrees to the terms of this EULA.

This license is effective until terminated. Licensor has the right to terminate your License immediately if you fail to comply with any term of this License.

"as is". Licensor makes no warranties, express or implied, arising from course of dealing or usage of trade, or statutory, as to any matter whatsoever. In particular, any and all warranties or merchantability, fitness for a particular purpose or non-infringement of third party rights are expressly excluded.

12. Governing Law

This License will be governed by the laws in force in Hong Kong. You hereby consent to the non-exclusive jurisdiction and venue sitting in Hong Kong to resolve any disputes arising under this EULA.


Should you have any questions concerning the validity of this License, please contact: licensing@navicat.com. If you desire to contact the Licensor for any other reason, please contact support@navicat.com.

PremiumSoft and other trademarks contained in the Software are trademarks or registered trademarks of PremiumSoft CyberTech Ltd. in the United States and/or other countries. Third party trademarks, trade names, product names and logos may be the trademarks or registered trademarks of their respective owners. You may not remove or alter any trademark, trade names, product names, logo, copyright or other proprietary notices, legends, symbols or labels in the Software. This EULA does not authorize you to use PremiumSoft or its licensors names or any of their respective trademarks.

Chapter 2 - User Interface

Main Window

The Main Window consists of several toolbars and panes for you to work on connections, database objects and advanced tools.



1 Main Toolbar

The Main Toolbar allows you to access basic objects and features, such as connections, users, tables, collections, backup, automation and more. To use small icons or hide the captions, right-click on the toolbar and disable **Use Big Icons** or **Show Caption**.

2 Navigation Pane

The Navigation Pane is the basic way to navigate with connections, databases and database objects. If the Navigation Pane is hidden, choose **View -> Navigation Pane -> Show Navigation Pane** from the menu bar.

3 Tab Bar

The Tab Bar allows you to switch among the tabbed windows on the Object Pane. You can choose to always display pop-ups on a new tab, or to always display them in a new window. If you have multiple tabs open, you can use CTRL+TAB to easily switch to other tabs. See also [Options](#).

4 Object Toolbar

The Object Toolbar provides other controls that you can use to manipulate the objects.

5 Object Pane

The Object Pane displays a list of objects (such as tables, collections, views, queries) and the tabbed window forms. Use the **List**, **Detail** and **ER Diagram** buttons to change the view of the Objects tab.

⑥ Information Pane

The Information Pane shows the detailed object information, project activities, the DDL of database objects, object dependencies, membership of users/roles and preview. If the Information Pane is hidden, choose **View -> Information Pane -> Show Information Pane** from the menu bar.

⑦ Status Bar

The Status Bar displays the current window's status information.

Navigation Pane

The Navigation pane employs tree structure which allows you to take action upon the database and their objects through their pop-up menus quickly and easily. If the **Show objects under schema in navigation pane** option is checked at the [Options](#) window, all database objects are also displayed in the pane. To connect to a database or schema, simply double-click it in the pane.

After logged in [Navicat Cloud](#) or [On-Prem Server](#), you can find it in the Navigation pane, and all connections stored locally will be located under the **My Connections** section.





Table elements, such as fields, indexes and foreign keys, are display under each table. Click the arrow to the left of the table name to expand the list. If the elements are hidden, enable the **Show objects under table in navigation pane** option in the [Options](#) window.

You can simply rename a field by using the pop-up menu, or you can double-click an element to open the table designer.



You can filter the tree by focusing the tree and type a search string. To show the opened objects only, choose **View -> Navigation Pane -> Show Only Active Objects** from the menu bar.

If you want to hide the group structure in the Navigation pane, choose **View -> Navigation Pane -> Flatten Connection**.

If the Navigation pane is hidden, choose **View -> Navigation Pane -> Show Navigation Pane**.

Object Pane

In the **Objects** tab, you can use the **List**, **Detail** and **ER Diagram** buttons to change the object view.

If you want to hide the group structure in List view or Details view, choose **View -> Flatten Object List** from the menu bar.

List View

By default, Navicat uses the **List** view. It only shows the names of objects.


Detail View

Detail view shows the name and several properties of objects in columns. To change the display columns of properties, choose **View -> Choose Columns** from the menu bar and choose display columns for different objects from the pop-up window.

ER Diagram View (Available only in Non-Essentials Edition)

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB. Only tables provide ER Diagram view.

An ER diagram will be generated automatically if the selected database/schema contains tables. ER diagram files are stored under [Settings Location](#).



① Diagram Canvas

Display table fields and relationships between tables in a database/schema graphically. You can add, edit or delete relations between tables, and also add or delete vertices on a relation line.

Add a Foreign Key

Click  from the bottom toolbar. Drag and drop a field from the child table to the parent table.

Edit or Delete a Foreign Key

Right-click a relation line and select **Design Foreign Key** or **Delete Foreign Key** from the pop-up menu.

Add or Delete a Vertex

Select a relation line or a vertex. Press and hold the SHIFT key and click on the relation line or the vertex.

Note: Double-click a table in the ER Diagram view will open the Table Designer, while double-click a table in the List or Detail view will open the Table Viewer.

② Overview

To zoom in or zoom out the selected area of the diagram, adjust the slider of the Overview. Same effect can be achieved with keyboard shortcuts:

Zoom In: [CTRL++] or [CTRL+Mousewheel up]

Zoom Out: [CTRL+-] or [CTRL+Mousewheel down]

Bottom Toolbar

Refresh

Refresh the ER diagram. Choose **Regenerate ER Diagram** to regenerate the ER diagram with using auto layout feature.

Move Diagram

Switch to hand mode for moving the diagram. Or, you can press and hold the SPACE key, then move the diagram.

New Relation

Add a relation between two table fields. Click this button, and then drag and drop a field from the child table to the parent table.

Color

Set the color of the selected tables or relations.





Paper Size








Select a paper size from the drop-down list. The corresponding paper size will reflect in the Overview.

Information Pane

The Information Pane shows the detailed object information, project activities, the DDL of database objects, object dependencies, membership of users/roles and preview. If the Information Pane is hidden, choose **View -> Information Pane -> Show Information Pane** from the menu bar.

You can select any connections, objects or projects, and then select the corresponding buttons on the Information Pane.

Button	Description
	General - Show the general information of the object/project.
	Preview - Show the SQL statements in the query.
	DDL - Show the DDL statements of the object. Press CTRL+F to open the search box.
	Using - Show the objects that the selected object depends on. Objects - Show the objects in the tablespace.

	Member Of - Show the roles that the user or the role assigned to.
	Used By - Show the objects that depend on the selected object. Members - Show the members of the role.
	Code Snippet - Show all built-in and custom code snippets . (Available only in Non-Essentials Edition)
	Identifiers - Show all available tables, collections, views or fields in the selected database or schema. Field - Show the information of the selected field in Table Viewer.
	Privileges - Show the privileges granted to the user.
	Project - Show the project members and the project activities done by the members. Click + to add members to the project.
	Type Color - Set the color of particular types for highlighting cells in Grid View . (Available only for MongoDB)
	Pub/Sub Info - Show which channels are active on the Redis server.

Chapter 3 - Collaboration

About Collaboration

Navicat allows you to synchronize connections, queries, snippets, models, workspaces and virtual groups from Navicat, other Navicat family members, different machines and different platforms. You can use Navicat Cloud to host the files. Or, if you have installed our another product, Navicat On-Prem Server, in your environment, you can hosts everything in-house.

Our collaboration feature allows you to give your teammates access to your projects when they log into their accounts. That way, you and your teammates can work on the same project without revealing your username and password. You can even choose to restrict the type of access your teammates have to your project.

Manage Cloud

Navicat Cloud

Navicat Cloud is a cloud service provided by PremiumSoft for synchronizing connections, queries, snippets, models, workspaces and virtual groups.

Navicat Cloud could not connect and access your databases. By which it means, it could only store your connection settings, queries, snippets, models, workspaces, and virtual groups; your database passwords and data (e.g. tables, views, etc) will not be stored to Navicat Cloud.

Note: You can only sign in to one Navicat Cloud account in the software. PremiumSoft will keep all synchronized files strictly confidential, and all employees are prohibited from viewing/accessing content of files you may store in your Navicat Cloud account.

Create Navicat Cloud Account

1. In the menu bar, choose **File** -> **Manage Cloud**.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Click **Create Navicat ID**.
4. Enter the required information and click **Sign Up**. A verification email will send to your email address.
5. Click the link in the email to verify the new account.

Hint: You can sign in with the same Navicat ID you use for the Navicat Customer Center.

Sign In Navicat Cloud

1. In the menu bar, choose **File** -> **Manage Cloud**.
2. In the Manage Cloud window, select **Navicat Cloud**.

3. Enter your **Navicat ID** and **Password**.
4. Click **Sign In**.
5. If you enabled two-step verification in [Navicat Cloud Portal](#), a code will be sent to your phone via your mobile app. Enter the received code to sign in.

Sign Out Navicat Cloud

1. In the main window, right-click **Navicat Cloud** and select **Close All Connections** to close all connections under Navicat Cloud.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select **Navicat Cloud**.
4. Click **Sign Out**.

View Usage

1. At the top right, click your avatar.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Your usage and current plan will be shown.

Change Your Picture

1. At the top right, click your avatar.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Click your avatar.
4. Choose an image file.

Manage Your Account

You can change your password, enable Two-Step Verification, upgrade Cloud Plan, etc in [Navicat Cloud Portal](#).

1. At the top right, click your avatar.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Click **Manage Account**.
4. A web browser will automatically open up to Navicat Cloud Portal.

On-Prem Server

Navicat On-Prem Server is an on-premise solution that provides you with the option to host a cloud environment for storing Navicat objects (connection settings, queries, snippets, models, workspaces, and virtual groups) internally at your location.

Before you can add an On-Prem Server, you must first set up Navicat On-Prem Server in your environment.

Note: You can add multiple On-Prem Server in the software.

Add New On-Prem Server

1. In the menu bar, choose **File -> Manage Cloud**.
2. In the Manage Cloud window, click **+ New On-Prem Server -> New On-Prem Server**.
3. Enter your On-Prem Server login information.

Option	Description
Host	The host name or IP address of your On-Prem Server.
Port	The port number of your On-Prem Server.
Verify Server Certificate	Enable this option to verify the server certificates.
Enable Push Synchronization	Navicat receives a silent push notification whenever its files stored in your On-Prem Server changes.

4. Click **OK**.

Add New On-Prem Server with URI

1. In the menu bar, choose **File -> Manage Cloud**.
2. In the Manage Cloud window, click **+ New On-Prem Server -> New On-Prem Server with URI**.
3. Paste your On-Prem Server URI.
4. Click **OK**.

Note: The URI can be copied from your On-Prem Server portal site.

Sign In On-Prem Server

1. In the menu bar, choose **File -> Manage Cloud**.
2. In the Manage Cloud window, select the On-Prem Server.
3. Enter your **Username** and **Password**.
4. Click **Sign In**.

5. If you enabled two-step verification, a code will be sent to you via the verification method you have selected.
Enter the received code to sign in.

Sign Out On-Prem Server

1. In the main window, right-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.

Edit On-Prem Server

1. In the main window, right-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.
5. Right-click your server and select **Edit On-Prem Server**.
6. Edit the On-Prem Server information.
7. Sign in your server.

Rename On-Prem Server

1. In the main window, right-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.
5. Right-click your server and select **Rename**.
6. Enter the name to describe your On-Prem Server.
7. Sign in your server.

Remove On-Prem Server

1. In the main window, right-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.
5. Right-click your server and select **Remove On-Prem Server**.
6. Click **Delete**.

View Usage

1. At the top right, click your avatar.
2. In the Manage Cloud window, select the On-Prem Server.
3. Your usage will be shown.

Change Your Picture

1. At the top right, click your avatar.
2. In the Manage Cloud window, select the On-Prem Server.
3. Click your avatar.
4. Choose an image file.

Manage Your Account

You can change your password, enable Two-Step Verification, etc in your On-Prem Server web portal.

1. At the top right, click your avatar.
2. In the Manage Cloud window, select the On-Prem Server.
3. Click **Manage Account**.
4. A web browser will automatically open up to your On-Prem Server web portal.

Push Synchronization

Push Synchronization enables Navicat to receive a silent push notification whenever the files stored in Navicat Cloud or On-Prem Server changes.

Enable Push Synchronization

1. At the top right, click your avatar.
2. In the Manage Cloud window, right-click Navicat Cloud or your On-Prem Server.
3. Turn on **Enable Push Synchronization**.

Disable Push Synchronization

1. At the top right, click your avatar.
2. In the Manage Cloud window, right-click Navicat Cloud or your On-Prem Server.
3. Turn off **Enable Push Synchronization**.

Cache and Local Copies

When you logged into Navicat Cloud or your On-Prem Server, Navicat saves the cloud object files and some information in the local computer. The cache and local copies use to make sure your changes are saved in the cloud.

Clear Cache and Local Copies

1. At the top right, click your avatar.
2. In the Manage Cloud window, select Navicat Cloud or your On-Prem Server.
3. Click **Sign Out**.
4. Right-click Navicat Cloud or your On-Prem Server and select **Clear Cache and Local Copies**.
5. Click **Clear**.

Open Containing Folder

1. In the main window, select Navicat Cloud or your On-Prem Server.
2. Open your project, connection, database and/or schema.
3. Click the Table, Model or Charts icon.
4. Right-click anywhere in the Objects tab and select **Open Containing Folder**.

Projects

Work With Projects

A project is a way to structure and organize Navicat objects. You can put related objects in one project, and then share the project with other accounts for collaboration if necessary.

Create New Projects

1. In the main window, right-click **Navicat Cloud** or your On-Prem Server.
2. Select **New Project**.
3. Enter the name of the new project.
4. Click **OK**.

Manage Existing Projects

To rename a project

1. In the main window, right-click the project and select **Rename**.
2. Enter a new project name.

Note: Only the project owner and the members with the *Can Manage & Edit* right can rename the project.

To delete a project

1. In the main window, right-click the project and select **Delete Project**.
2. Click **Delete**.

Note: Only the project owner can delete the project.

Note: Before you delete the project, you must remove all objects in the project.

To quit a project

1. In the main window, right-click the project and select **Quit Project**.
2. Click **Quit**.

Manage Members

Add Members

1. In the main window, right-click the project and select **Manage Members**.
2. Click **Add Members**.
3. [Navicat Cloud] Enter the member's Navicat ID and press ENTER.
4. [On-Prem Server] Check the boxes of the users that you want to add.
5. Select the member right.
6. Click **Add**.

Member Rights	Privileges
Can Manage & Edit	Read Objects, Write Objects, Manage Members and Rename Projects
Can Edit	Read Objects and Write Objects
Can View	Read Objects

Manage Existing Members

To edit the right of a member

1. In the main window, right-click the project and select **Manage Members**.
2. Use the drop-down list next to the member to change the right.
3. Click **Apply**.

To remove a member from a project


1. In the main window, right-click the project and select **Manage Members**.
2. Click the **X** icon next to the member.
3. Click **Apply**.

Chapter 4 - Connection

About Connection

To start working with your server in Navicat, you should first establish a connection or several connections using the Connection window. If you are new to the server or 'Net in general' and are not quite sure how things work, you may want to look at:

- [MySQL User Manual](#)
- [Oracle Database Documentation](#)
- [PostgreSQL User Manual](#)
- [SQLite User Manual](#)
- [Microsoft SQL documentation](#)
- [MariaDB Documentation](#)
- [MongoDB Manual](#)
- [Redis Documentation](#)

To create a new connection, click  **Connection** and select your server type. Then, enter the necessary information in the Connection window.

Note: Navicat authorizes you to make connection to remote servers running on different platforms (i.e. Windows, macOS, Linux and UNIX), and supports PAM and GSSAPI authentication.

You can edit the connection properties by right-click the connection and select **Edit Connection**.

Move / Copy Connection To Project

If you have logged in to Navicat Cloud or On-Prem Server, you can synchronize the connection in My Connections to a project.

1. Right-click a connection under **My Connections** and select **Move Connection To** or **Copy Connection To**.
2. Select an existing project or create a new project.
3. Choose whether to include all queries and virtual groups in the connection and click **OK**.
4. The connection will be moved or copied to the project.

Hint: You can move / copy a connection in a project to My Connections in a similar way.

Flush MySQL/MariaDB Connection

To clear or reload various internal caches, flush tables, or acquire locks, right-click your connection in the Navigation pane and select **Flush** and choose the flush option. You must have the [RELOAD](#) privilege to use this feature.

Manage Azure SQL Database Firewall Rules

You cannot connect to Azure SQL Database until you have granted your client IP access. To access Azure SQL Database from your computer, ensure that your firewall allows outgoing TCP communication on TCP port 1433. You must have at least one firewall rule before you can connection to Azure SQL Database.

To manage the Firewall Rule settings, right-click your Azure SQL Database connection in the Navigation pane and select **SQL Azure Firewall Rules**. Add a new rule by providing an IP address range.

Testing Account

Navicat provides evaluated accounts for testing purpose.

MySQL

- Host: server1.navicat.com
- Port: 4406
- User Name: navicat
- Password: testnavicat

PostgreSQL

- Host: server1.navicat.com
- Port: 5432
- Initial Database: HR
- User Name: navicat
- Password: testnavicat

General Settings

RDBMS

To successfully establish a new connection to local/remote server - no matter via SSL, SSH or HTTP, set the database login information in the General tab. If your Internet Service Provider (ISP) does not provide direct access to its server, Secure Tunneling Protocol (SSH) / HTTP is another solution.

Note: The following options depend on the connection server type and sort in ascending order.

Add To

After you logged in [Navicat Cloud](#) or [On-Prem Server](#), you can choose to save the connection to My Connections or a project.

Authentication

SQL Server Authentication	Use login records to validate the connection. Users must provide their server login: User Name and Password .
Windows Authentication	When a user connects through a Windows user account, SQL Server validates the account name and password using the Windows principal token in the operating system.

Connection Name

Enter a friendly name to best describe your connection.

Connection Type

Basic	In Basic mode, it connects to Oracle through the Oracle Call Interface (OCI). Enter the Host and Port . Set the Service Name/SID which the user connects when making connection. Select the corresponding radio button.
TNS	In TNS mode, it connects to Oracle server using an alias entry from a tnsnames.ora file through the Oracle Call Interface (OCI). User needs to provide the Net Service Name .

OCI is an application programming interface that allows an application developer to use a third-generation language's native procedure or function calls to access the Oracle database server and control all phases of SQL statement execution. OCI is a library of standard database access and retrieval functions in the form of a dynamic-link library. See also: [OCI options](#)

Database File

Specify the initial database file. If the HTTP Tunnel is enabled, you need to enter an absolute file path of the database file in your web server.

Endpoint

The Endpoint for connecting to the Amazon Web Services instance.

Host

A host name where the database is situated or the IP address of the server.

Initial Database

Set the initial database which user connects when making connection.

Password

Password for connecting to the database server.

Port

A TCP/IP port for connecting to the database server.

Type

Existing Database File	Connect to an existing database in the Database File .
New SQLite 3	Create a new SQLite 3 database in the Database File .
New SQLite 2	Create a new SQLite 2 database in the Database File .

User Name

User name for connecting to the database server.

MongoDB

To successfully establish a new connection to local/remote server - no matter via SSL or SSH, set the database login information in the General tab. If your Internet Service Provider (ISP) does not provide direct access to its server, Secure Tunneling Protocol (SSH) is another solution.

Connection Name

Enter a friendly name to best describe your connection.

Add To

After you logged in [Navicat Cloud](#) or [On-Prem Server](#), you can choose to save the connection to My Connections or a project.

Connection

The type of your MongoDB server: Standalone, Shard Cluster or Replica Set.

SRV Record

Check this option to connect the server using an SRV Record.

Host

A host name, IP address, or UNIX domain socket of the server.

Port

A TCP/IP port for connecting to the server.

Member

Add or remove the members of replica set or the instances of sharded cluster to the connection.

Read Preference

Choose the replica set read preference for this connection.

Replica Set

The name of the replica set.

Authentication

Choose the authentication mechanism that MongoDB will use to authenticate the connection.

None	No authentication.
Password	Specify the Authentication Database name associated with the User Name and Password .
LDAP	Specify the User Name and Password .
Kerberos	Set the Kerberos Service Name and the user Principal .
X.509	x.509 certificate authentication.

Use MongoDB URI

You can also use a MongoDB URI to connect your MongoDB server. Simply click the **URI** button and paste the URI. Navicat will automatically fill out the options in the General, SSL and SSH tabs.

Redis

To successfully establish a new connection to local/remote server - no matter via SSL or SSH, set the database login information in the General tab. If your Internet Service Provider (ISP) does not provide direct access to its server, Secure Tunneling Protocol (SSH) is another solution.

Connection Name

Enter a friendly name to best describe your connection.

Add To

After you logged in [Navicat Cloud](#) or [On-Prem Server](#), you can choose to save the connection to My Connections or a project.

Host

A host name, IP address, or UNIX domain socket of the server.

Port

A TCP/IP port for connecting to the server.

Authentication

Choose the authentication mechanism that Redis will use to authenticate the connection.

None	No authentication.
Password	Enter the Password if the Redis server is password protected via the requirepass option.
Username & Password	Enter the User Name and Password if Redis ACLs are used.

Advanced Settings

Note: The following options depend on the connection server type and sort in ascending order.

Auto connect

Open the connection at application startup automatically.

Client Character Set

Choose the session client character set used in Navicat.

Client Driver Version

Choose the client driver used to connect the server. If the default driver does not work, you can change this setting to Legacy.

Compatibility

Enable the Compatibility tab for setting the compatibility mode for MySQL connection.

Connection Timeout

Specify the amount of time to wait for a connection to be established before timing out.

Encoding

Choose a codepage for converting data to display in Navicat UI.

Encrypted

Enable this option and provide **Password** when connecting to an encrypted SQLite database.

Execution Timeout

Specify the amount of time to wait before execution of a task is completed on the server.

Keepalive interval

Keep the connection with the server alive by pinging it. You can set the period between pings in the edit box.

Limit connection sessions

Specify the maximum number of concurrent connections that the server allows.

Native Client Driver

Choose the SQL Server Native Client used for the connection.

OS authentication

Use OS user login credentials to authenticate database users.

Read Timeout

Specify the amount of time to wait for more data from a connection before aborting the read.

Retryable Reads

Disable this option to specify "retryReads=false" in the connection string.

Retryable Writes

Disable this option to specify "retryWrites=false" in the connection string.

Role

Indicate that the database user is connecting with either the Default, SYSOPER or SYSDBA system privilege.

Server Selection Timeout

Specify the amount of time to block for server selection before throwing an exception.

Settings Location

When a new connection is being established, Navicat will create a subfolder under the Settings Location. Most files are stored within this subfolder:

File in Settings Location	Server Type	File Extension
Backup	MySQL, PostgreSQL, SQLite and MariaDB	.nb3
	Redis	.nbr
Backup Profile	MySQL	.nbakmysql
	PostgreSQL	.nbakpgsql
	SQLite	.nbaksqlite
	SQL Server	.nbakmssql
	MariaDB	.nbakmariadb

	Redis	.nbakredis
Data Pump Export Profile	Oracle	.nbakora
Data View Profile	Redis	.ndvredis
ER Diagram File	MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB	.ned
Export Materialized View Profile	Oracle	.nexpmora
	PostgreSQL	.nexpmpgsql
Export Query Result Profile	MySQL	.nexpqmysql
	Oracle	.nexpqora
	PostgreSQL	.nexpqpgsql
	SQLite	.nexpqsqlite
	SQL Server	.nexpqmssql
	MariaDB	.nexpqmariadb
	MongoDB	.nexpqmongodb
Export Table/Collection Profile	MySQL	.nexptmysql
	Oracle	.nexptora
	PostgreSQL	.nexptpgsql
	SQLite	.nexptsqlite
	SQL Server	.nexptmssql
	MariaDB	.nexptmariadb
	MongoDB	.nexptmongodb
Export View Result Profile	MySQL	.nexpvmysql
	Oracle	.nexpvora
	PostgreSQL	.nexpvpgsql
	SQLite	.nexpvsqlite
	SQL Server	.nexpvmssql
	MariaDB	.nexpvmariadb
	MongoDB	.nexpvmongodb
Import Table/Collection Profile	MySQL	.nimpmysql
	Oracle	.nimpora
	PostgreSQL	.nimpppgsql
	SQLite	.nimpsqlite
	SQL Server	.nimpmssql
	MariaDB	.nimpmariadb
	MongoDB	.nimpmongodb
MapReduce	MongoDB	.mapreduce
Pub/Sub	Redis	.npsbredis
Pub/Sub Archive File	Redis	.nrpsbmlog
Query	MySQL, Oracle, PostgreSQL, SQLite, SQL Server and	.sql

	MariaDB	
	MongoDB	.js
	Redis	.redis
Schema Analysis	MongoDB	.nsatmongodb

Socket Timeout

Specify the amount of time to wait for an inactive socket before closing it.

Trust Server Certificate

Skip the step that validates the server certificate. The server certificate is automatically trusted.

Use compression

Use compression protocol. It is used if both client and server support zlib compression, and the client requests compression.

Use encryption

Use encryption for SQL Server connection.

Use named pipe, socket

Use socket file for localhost connection.

Write Timeout

Specify the amount of time to wait for a block to be written to a connection before aborting the write.

Databases / Attached Databases Settings

MySQL, Oracle, PostgreSQL, SQL Server, MariaDB, MongoDB, Redis

In the **Databases** tab, you can set which databases will be shown in the Navigation pane when connecting to your server. It is not obligatory. To start working with custom database settings, check **Use custom database list**. Then, check the preferable databases in the **Database** column. If you want Navicat automatically open the databases at connection, check the **Auto Open** box.

Add a hidden database to the list

1. Click the **Add Database to List** button.
2. Enter the database name.
3. Check the newly added database in the database list.

Remove a database from the list

1. Select the database in the database list.
2. Click the **Remove Database from List** button.

Note: The database will be just removed from the database list box, it will still exist in the server.

SQLite

In the **Attached Databases** tab, you can attach SQLite database files to the connection. Click the **Attach Database** button and enter the information:

Option	Description
Database File	Choose the file path of a database file.
Database Name	Enter the database name which displays in Navicat.
Encrypted	Check this option and provide the Password if the database file is encrypted.

To detach a database, select it from the list and click the **Detach Database** button.

SSL Settings

Secure Sockets Layer(SSL) is a protocol for transmitting private documents via the Internet. To get a secure connection, the first thing you need to do is to install OpenSSL Library and download Database Source.

Note: Available only for MySQL, PostgreSQL, MariaDB, MongoDB and Redis. Support from PostgreSQL 8.4 or later.

MySQL and MariaDB Connections

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The SSL key file in PEM format to use for establishing a secure connection.

Client Certificate

The SSL certificate file in PEM format to use for establishing a secure connection.

CA Certificate

The path to a file in PEM format that contains a list of trusted SSL certificate authorities.

Verify server certificate against CA

Check the server's Common Name value in the certificate that the server sends to the client.

Specified Cipher

A list of permissible ciphers to use for SSL encryption.

PostgreSQL Connection

Choose the **SSL Mode**:

require	Only try an SSL connection.
verify-ca	Only try an SSL connection, and verify that the server certificate is issued by a trusted CA.
verify-full	Only try an SSL connection, verify that the server certificate is issued by a trusted CA and that the server hostname matches that in the certificate.

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The path of the client private key.

Client Certificate

The path of the client certificate.

Root Certificate

The path of the trusted certificate authorities.

Certificate Revocation List

The file path of the SSL certificate revocation list (CRL).

MongoDB Connection

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The SSL key file in PEM format to use for establishing a secure connection.

Client Key Password

The password of the key file.

Allow any server SSL certificates

Check this option if your MongoDB server allows any server SSL certificates.

CA Certificate

The path to a file in PEM format that contains a list of trusted SSL certificate authorities.

Certificate Revocation List

The file path of the SSL certificate revocation list (CRL).

Allow invalid host names

Check this option to allow invalid hostnames in SSL certificates.

Redis Connection

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The SSL key file in PEM format to use for establishing a secure connection.

Client Key Password

The password of the key file.

Allow any server SSL certificates

Check this option if your Redis server allows any server SSL certificates.

CA Certificate

The path to a file in PEM format that contains a list of trusted SSL certificate authorities.

Server Name Indication

The Server Name Indication (SNI) value used when establishing the SSL connection to the Redis server.

SSH Settings

Secure SHell (SSH) is a program to log in into another computer over a network, execute commands on a remote server, and move files from one machine to another. It provides strong authentication and secure encrypted communications between two hosts, known as **SSH Port Forwarding (Tunneling)**, over an insecure network. Typically, it is employed as an encrypted version of Telnet.

In a Telnet session, all communications, including username and password, are transmitted in plain-text, allowing anyone to listen-in on your session and steal passwords and other information. Such sessions are also susceptible to session hijacking, where a malicious user takes over your session once you have authenticated. SSH serves to prevent such vulnerabilities and allows you to access a remote server's shell without compromising security.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server, MariaDB, MongoDB and Redis.

Please make sure that the parameter - "AllowTcpForwarding" in the Linux server must be set to value "yes", otherwise, the SSH port forwarding will be disabled. To look for the path: /etc/ssh/sshd_config. By default, the SSH port forwarding should be enabled. Please double check the value settings.

Even the server support SSH tunnel, however, if the port forwarding being disabled, Navicat cannot connect via SSH Port 22.

Host

A host where SSH server is activated.

Note: The host name in the General tab should be set relatively to the SSH server which provided by your database hosting company.

Port

A port where SSH server is activated, by default it is 22.

User Name

A user on SSH server machine. (It is not a user of database server.)

Authentication Method

Password	Provide the SSH server user Password .
Public Key	Private Key It is used together with your public key. The private key should be readable only by you. Passphrase A passphrase is exactly like a password, except that it applies to the keys you are generating and not an account.

Note: HTTP Tunnel and SSH Tunnel cannot be function simultaneously. The SSH Tunnel is disabled when you select the HTTP Tunnel and vice versa.

HTTP Settings

HTTP Tunneling is a method for connecting to a server that uses the same protocol (http://) and the same port (port 80) as a web server does. It is used while your ISPs do not allow direct connections, but allows establishing HTTP connections.

Note: Available only for MySQL, PostgreSQL, SQLite and MariaDB.

Uploading the Tunneling Script

To use this connection method, first thing you need to do is to upload the tunneling script to the web server where your server is located.

Note: **ntunnel_mysql.php** (for both MySQL and MariaDB), **ntunnel_pgsql.php** or **ntunnel_sqlite.php** is available in the Navicat installation folder.

Setting up HTTP Tunnel

The following instruction guides you through the process of configuring a HTTP connection.

1. Select the HTTP tab and enable **Use HTTP tunnel**.
2. Enter URL of the tunneling script.
e.g. `http://www.navicat.com/ntunnel_mysql.php`
3. If your server installed a Web Application Firewall, you can check the **Encode outgoing query with base64** option.
4. If the tunneling script is hosted in a password protected server or you have to access internet over a proxy server, you can provide the required authentication details in the **Authentication** or **Proxy** tab.

Note: HTTP Tunnel and SSH Tunnel cannot be function simultaneously. The SSH Tunnel is disabled when you select the HTTP Tunnel and vice versa.

Compatibility Settings

If your server is a variant of MySQL or has proxy middleware installed, you can enable compatibility mode and set the corresponding settings for the connection.

Note: Available only for MySQL.

Force lower_case_table_names as

Set the value of the lower_case_table_name system variable.

Force sql_mode as

Set the value of the sql_mode system variable.

Force NDB cluster support as

Include or exclude the support for the NDBCLUSTER storage engine.

Force database listing method as

Use the SHOW DATABASES statement to retrieve the information for listing databases, or select the information from the INFORMATION_SCHEMA database.


Force view listing method as

Use the SHOW FULL TABLES statement to retrieve the information for listing tables, or select the information from the INFORMATION_SCHEMA database.

Connect with Different Profiles

You can have multiple profiles for each connection, with slightly different connection settings. For example, different database users.

Create Connection Profile

1. In the connection window, click .
2. Click **+ New Connection Profile -> New Profile / Duplicate Profile**.
3. Enter the name of the profile.
4. Enter the connection settings.
5. Click **OK**.

Switch Profile

1. In the main window, right-click a connection and select **Switch Connection Profile**.
2. Select the profile name.

Hint: You can also set the default active profile in the connection window.

Chapter 5 - Server Objects

About Server Objects

Navicat provides powerful tools to manage server objects, such as databases, tables, views, functions, etc.

Some server objects may have been hidden by Navicat. These objects include system databases, system tables and so on. To show the hidden items, choose **View -> Show Hidden Items** from the menu bar.

Note: Before working with the server objects in Navicat, you should establish the connection first.

In object designers, you can preview the necessary SQL statements, scripts or commands for creating or editing the object on the **SQL Preview**, **Script Preview** or **Command Preview** tab. For some database or schema objects, you can use the bottom drop-down list to show the SQL, scripts or commands which will be run when choosing **Save** or **Save As** from the **File** menu.

MySQL / MariaDB

Databases

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database.

Create a new database


1. In the Navigation pane, right-click your connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Edit an existing database

1. In the Navigation pane, right-click a database and select **Edit Database**.
2. Edit the database properties in the pop-up window.

Note: MySQL does not support renaming database through its interface at this moment. Access the directory in which databases being stored. By default, all databases store within a directory called data under MySQL Installation folder. For example: C:\mysql5\data. You must stop MySQL before you can rename the database.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

There are two ways to open a table with graphical fields, right-click a table and select:

Option	Description
--------	-------------

Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the SHIFT key when right-clicking the table.)

You can create a table shortcut by right-clicking a table in the Object pane and select **Create Open Table Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, right-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.

In the **Fields** tab, you can search a field name by choosing **Edit -> Find** or pressing CTRL+F.


Note: The tabs and options in the designer depend on the server type and version.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Note: Transaction is only available for INNODB tables.


Views




A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by right-clicking a view in the Objects tab and select **Create Open View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your view directly without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
 Preview	Preview the data of the view.

 Explain	Show the Query Plan of the view.
 View Builder	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.


Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Note: Transaction is only available for updatable views.

Procedures / Functions

Procedures and functions (stored routines) are supported in MySQL 5.0. A stored routine is a set of SQL statements that can be stored in the server. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  **New Function** from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.


1. Select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Mode**, **Name** and/or **Type** under the corresponding columns.
3. If you create a function, select the **Return Type** from the list and enter the corresponding information: **Length**, **Decimals**, **Character set** and/or **Enum**.

Hint: Once uncheck the **Show wizard next time** option, you can go to [Options](#) to enable it.

Function Designer

Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. This can be a simple statement such as SELECT or INSERT, or it can be a compound statement written using BEGIN and END. Compound statements can contain declarations, loops, and other control structure statements. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.


Results

To execute the procedure/function, click  **Execute** on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the

procedure/function requires input parameters, the **Input Parameter** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.

Note: Navicat supports to return 20 result sets.


Tablespaces

An InnoDB general tablespace is a shared tablespace which can hold multiple tables, and supports all table row formats. An InnoDB undo tablespace contains undo logs. In MySQL NDB Cluster, tablespace can contain one or more data files, providing storage space for NDB Cluster Disk Data table. In the main window, click  **Others** -> **Tablespace** to open the tablespace object list.

Tablespace Designer

Tablespace Designer is the basic Navicat tool for working with tablespaces. It allows you to set the table engine, specify the data file, etc.


Events

An event is a task that run according to a schedule. In the main window, click  **Others** -> **Event** to open the event object list.

Event Designer

Event Designer is the basic Navicat tool for working with events. You can enter a valid SQL procedure statement in the **Definition** tab. This can be a simple statement such as SELECT or INSERT, or it can be a compound statement written using BEGIN and END. Compound statements can contain declarations, loops, and other control structure statements. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

Other Objects

Navicat also allows you to manage other MySQL / MariaDB objects: Sequence. In the main window, click  **Others** and select an object to open the object list.

Note: Sequences are available for MariaDB 10.3 or later.

Maintain Objects

Navicat provides a complete solution for maintaining MySQL / MariaDB objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Right-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Table

Option	Description
Analyze Tables	Analyze and store the key distribution for the table.
Check Tables	Check the table for errors.
Optimize Tables	Optimize the table to reduce storage space and improve I/O efficiency.
Repair Tables	Repair the possibly corrupted table.
Get Rows Count	Count the number of rows in the table.

Tablespace

Option	Description
Set Active	Mark an InnoDB undo tablespace as active.
Set Inactive	Mark an InnoDB undo tablespace as inactive.


Oracle

Schemas

To start working with the server objects, you should create and open a connection. When you create a user account, you are also implicitly creating a schema for that user. A schema is a logical container for the database objects (such as tables, views, triggers, and so on) that the user creates. The schema name is the same as the user name, and can be used to unambiguously refer to objects owned by the user.

Hint: Oracle interprets non-quoted object identifiers as uppercase. In Navicat, all object identifiers will be quoted. That is, Navicat saves exactly what you have inputted.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

You can create **Normal** / **External** / **Index Organized** tables. Click the down arrow next to  **New Table** from the object toolbar and choose the table type.

There are two ways to open a table with graphical fields, right-click a table and choose:

Option	Description
Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the SHIFT key when right-clicking the table.)

You can create a table shortcut by right-clicking a table in the Object pane and select **Create Open Table Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, right-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find** or pressing CTRL+F. When creating a new table, you are allowed to insert fields or rearrange the order of the fields.

Note: The tabs and options in the designer depend on the server version and the table type.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.





Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by right-clicking a view in the Objects tab and select **Create Open View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your view directly without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.


Button	Description
 Preview	Preview the data of the view.
 Explain	Show the Query Plan of the view.
 View Builder	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.

Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Materialized Views





Materialized Views are schema objects that used to summarize, compute, replicate, and distribute data. In the main window, click  **Materialized View** to open the materialized view object list.

You can create a materialized view shortcut by right-clicking a materialized view in the Objects tab and select **Create Open Materialized View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your materialized view directly without activating the Navicat main window.

To refresh a materialized view, right-click it in the Objects tab and select **Refresh Materialized View** from the pop-up menu.

Materialized View Designer

Materialized View Designer is the basic Navicat tool for working with materialized views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.


Button	Description
 Preview	Preview the data of the materialized view.
 Explain	Show the Query Plan of the materialized view.
 View Builder	Build the materialized view visually. It allows you to create and edit materialized views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.

Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

Materialized View Viewer

When you open a materialized view, **Materialized View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Procedures / Functions

Procedures and functions are schema objects that consist a set of SQL statements and stored in the server. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  **New Function** from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.

1. Specify the **Name** of the routine and select the type of the routine: **Procedure** or **Function**.

2. Define the parameters. Set the **Name**, **Type**, **Mode** and **Default Value** under the corresponding columns.
3. If you create a function, select the **Return Type** from the list.







Hint: Once uncheck the **Show wizard next time** option, you can go to [Options](#) to enable it.

Function Designer


Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

The **Code Outline** pane displays information about the procedure/function including parameters, code body, etc. If the Code Outline pane is hidden, choose **View -> Code Outline**.

Note: Available only in Non-Essentials Edition.


Button	Description
	Refresh the code outline.
	Show the detail view of the code outline.
	Turn mouse over highlight on or off.
	Expand the selected item.
	Collapse the selected item.
	Toggle sorting by position.



Results

To execute the procedure/function, click  **Execute** on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **DBMS Output** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the procedure/function requires input parameters, the **Input Parameter** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.


Note: Navicat supports to return 20 result sets.

Debug (Available only in Non-Essentials Edition)



You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.


Before debugging, click  **Save As Debug** to save and compile the procedure/function. Then, click  **Debug** on the toolbar to launch the [Oracle Debugger](#). Enter the input parameters if necessary.

Packages

Packages are encapsulated collections of related procedures, stored functions, and other program objects stored together in the database. A package consists of two parts: a specification and a body. In the main window, click  **Others** -> **Package** to open the package object list.

Package Designer & Package Body Designer







Package Designer and **Package Body Designer** are the basic Navicat tools for working with packages. After saving the package in Package Designer, you can edit its package body by clicking  **New Package Body** or  **Design Package Body**.

Likewise, you can edit its package specification by clicking  **Design Package Specification** in Package Body Designer.


You can enter a valid SQL statement in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

The **Code Outline** pane displays information about the package/package body including function, procedure, parameter, code body, etc. If the Code Outline pane is hidden, choose **View -> Code Outline**.


Note: Available only in Non-Essentials Edition.



Button	Description
	Refresh the code outline.
	Show the detail view of the code outline.
	Turn mouse over highlight on or off.
	Expand the selected item.
	Collapse the selected item.
	Toggle sorting by position.

Results


To execute the package, click  **Execute** on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **DBMS Output** tab opens with the data returned. If an error occurs while executing the package, execution stops, the appropriate error message is displayed. If the package requires input parameters, the **Input Parameter** dialog will pop up.

Debug (Available only in Non-Essentials Edition)

You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.

Before debugging, click  **Save As Debug** to save and compile the package. Then, click  **Debug** on the toolbar to launch the [Oracle Debugger](#). Enter the input parameters if necessary.

Recycle Bin


Recycle bin contains dropped tables and any associated objects such as indexes, constraints, nested tables. In the main window, click  **Others -> Recycle Bin** to open the recycle bin object list.

Restore a table

1. Select a table in the Objects tab.

2. Click  **Flashback Table**.

Remove an object

1. Select an object for purging in the Objects tab.
2. Click  **Purge Object**.
3. Confirm deleting in the dialog window.


Remove all objects

1. Right-click anywhere in the Objects tab and select **Purge Recycle Bin** from the pop-up menu.
2. Confirm deleting in the dialog window.

Remove all objects of any users

1. Log in a user with SYSDBA privilege.
2. Right-click anywhere in the Objects tab and select **Purge DBA Recycle Bin** from the pop-up menu.
3. Confirm deleting in the dialog window.

Other Objects

Navicat also allows you to manage other Oracle objects: Database Link, Index, Java, Materialized View Log, Sequence, Synonym, Trigger, Type, XML Schema, Directory, Public Database Link, Public Synonym and Tablespace. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining Oracle objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Right-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Table

Option	Description
Enable Table Lock	Allow DDL operations on the table.
Disable Table Lock	Prevent DDL operations on the table.
Enable Row Movement	Allow the database to move a row, thus changing the rowid.
Disable Row Movement	Prevent the database from moving a row, thus preventing a change of

	rowid.
Shrink Space	Shrink space in the table.
Move	Relocate data of the table.
Collect Statistics	Analyze the contents of the table.
Validate Structure	Verify the integrity of the structure of the table.

View

Option	Description
Compile	Recompile the view specification or body.

Procedure / Function

Option	Description
Compile	Recompile the specification or body.
Compile for Debug	Recompile the specification or body. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.

Index

Option	Description
Rebuild	Re-create the index or one of its partitions or subpartitions.
Make Unusable	Make the index unusable.
Coalesce	Merge the contents of index blocks where possible to free blocks for reuse.
Compute Statistics	Compute the statistics of the index.
Monitoring Usage	Begin monitoring the index.
No Monitoring Usage	Terminate monitoring the index.

Java

Option	Description
Compile or Resolve	Resolve the primary Java class schema object.
Set AuthID Current User	Set the invoker rights to AUTHID CURRENT_USER.
Set AuthID Definer	Set the invoker rights to AUTHID DEFINER.

Materialized View

Option	Description
Enable Row Movement	Allow the database to move a row, thus changing the rowid.
Disable Row Movement	Prevent the database from moving a row, thus preventing a change of rowid.
Shrink	Compact the materialized view segment.
Compile	Revalidate the materialized view.
Force Refresh	Refresh the materialized view.

Materialized View Log

Option	Description
Enable Row Movement	Allow the database to move a row, thus changing the rowid.
Disable Row Movement	Prevent the database from moving a row, thus preventing a change of rowid.
Shrink Space	Compact the materialized view log segments.

Package

Option	Description
Compile	Recompile the package specification and body.
Compile for Debug	Recompile the package specification and body. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.

Trigger

Option	Description
Enable	Enable the trigger.
Disable	Disable the trigger.
Compile	Recompile the trigger.
Compile for Debug	Recompile the trigger. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.

Type

Option	Description
Compile	Recompile the type specification and body.
Compile for Debug	Recompile the type specification and body. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.

XML Schema

Option	Description
Compile	Recompile the already registered XML schema.
Purge	Removes the XML schema completely from Oracle XML DB.

Tablespace

Option	Description
Read Only	Place the tablespace in transition read-only mode.
Read Write	Allow write operations on a previously read-only tablespace.
Online	Take the tablespace online.
Offline	Take the tablespace offline.
Coalesce	Combine all contiguous free extents into larger contiguous extents for each datafile in the tablespace.
Shrink Space	Reduce the amount of space the tablespace is taking.

PostgreSQL

Databases & Schemas

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database and/or a new schema.

Create a new database

1. In the Navigation pane, right-click a connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Edit an existing database

1. In the Navigation pane, right-click a database and select **Edit Database**.
2. Edit the database properties in the pop-up window.


Create a new schema


1. In the Navigation pane, right-click a database and select **New Schema**.
2. Enter the schema properties in the pop-up window.

Edit an existing schema

1. In the Navigation pane, right-click a schema and select **Edit Schema**.
2. Edit the schema properties in the pop-up window.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

You can create **Normal** / **Foreign** / **Partitioned** tables. Click the down arrow next to  **New Table** from the object toolbar and choose the table type.

There are two ways to open a table with graphical fields, right-click a table and choose:

Option	Description
Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the SHIFT key when right-clicking the table.)

You can create a table shortcut by right-clicking a table in the Objects tab and select **Create Open Table Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, right-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find** or pressing CTRL+F. When creating a new table, you are allowed to insert fields or rearrange the order of the fields.

Note: The tabs and options in the designer depend on the server version and the table type.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.





Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by right-clicking a view in the Objects tab and select **Create Open View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your view directly without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.


Button	Description
 Preview	Preview the data of the view.
 Explain	Show the Query Plan of the view.
 View Builder	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.

Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Materialized Views





Materialized Views are schema objects that used to summarize, compute, replicate, and distribute data. In the main window, click  **Materialized View** to open the materialized view object list.

You can create a materialized view shortcut by right-clicking a materialized view in the Objects tab and select **Create Open Materialized View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your materialized view directly without activating the Navicat main window.

To refresh and completely replace the contents of a materialized view, right-click it in the Objects tab and select **Refresh Materialized View With -> Data** or **No Data** from the pop-up menu.

Materialized View Designer

Materialized View Designer is the basic Navicat tool for working with materialized views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.


Button	Description
 Preview	Preview the data of the materialized view.
 Explain	Show the Query Plan of the materialized view.
 View Builder	Build the materialized view visually. It allows you to create and edit materialized views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.

Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

Materialized View Viewer

When you open a materialized view, **Materialized View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Procedures / Functions

Procedures and functions are schema objects that consist a set of SQL statements and stored in the server. Procedures are supported in PostgreSQL 11. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  **New Function** from the object toolbar. **Function Wizard** will pop up and it allows you to create a function easily.


1. Select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Mode**, **Type**, **Schema**, **Type**, **Name** and **Default Value** under the corresponding columns.
3. If you create a function, select the **Schema** and **Return Type** from the list.

Hint: Once uncheck the **Show wizard next time** option, you can go to [Options](#) to enable it.

Function Designer

Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. This can be a simple statement such as SELECT or INSERT, or it can be a compound statement written using BEGIN and END. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

Results


To execute the procedure/function, click  **Execute** on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the procedure/function requires input parameters, the **Input Parameter** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.


Note: Navicat supports to return 20 result sets.

Debug (Available only in Non-Essentials Edition)


Before debugging PL/pgSQL procedures/functions, you need to install the pldbgapi extension. You can right-click anywhere in the function object list and select **Install pldbgapi Extension**.


Note: This option is only available for PostgreSQL 9.1 or later. If your server is PostgreSQL 8.3 to 9.0, you need to enable the debugger plugin manually in the server.

Then, open a PL/pgSQL procedure/function. You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.

Click  **Debug** on the toolbar to launch the [PostgreSQL Debugger](#).

Types

Types register new data types for use in the current database. In the main window, click  **Others -> Type** to open the type object list.


You can create **Base** / **Composite** / **Enum** / **Range** types. Click the down arrow next to  **New Type** from the object toolbar and choose the type.

Type Designer

Type Designer is the basic Navicat tool for working with types. It allows you to create or edit a type.

Note: The tabs and options in the designer depend on the server version and the type you are chosen.

Foreign Servers


A foreign server typically encapsulates connection information that a foreign-data wrapper uses to access an external data resource. In the main window, click  **Others** -> **Foreign Server** to open the foreign server object list.

To install the `postgres_fdw` extension for accessing data stored in external PostgreSQL servers, you can right-click anywhere in the foreign server object list and select **Install postgres_fdw Extension**.

Foreign Server Designer

Foreign Server Designer is the basic Navicat tool for working with foreign servers. It allows you to create or edit a foreign server.

Other Objects

Navicat also allows you to manage other PostgreSQL objects: Aggregate, Conversion, Domain, Index, Operator, Operator Class, Sequence, Trigger, Tablespace, Cast and Language. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining PostgreSQL objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Right-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Allow	Users can connect to the database.
Disallow	No users can connect to the database.
Analyze Database	Collect statistics about the database.
Vacuum Database	Garbage-collect and optionally analyze the database.
Reindex Database	Recreate all indexes within the database.

Table / Materialized View

Option	Description
Analyze Tables / Analyze Materialized Views	Collect statistics about the contents of the table.
Vacuum Tables / Vacuum Materialized Views	Garbage-collect and optionally analyze the table.
Reindex Tables / Reindex Materialized Views	Recreate all indexes of the table.

Manage Extensions

PostgreSQL has various extensions, supplying extra functions, operators, or types to extend the functionality of a database. You can install the extensions that are supported by your PostgreSQL server.

Install an extension

1. In the Navigation pane, right-click a database and select **Manage Extensions**.
2. All available extensions are listed on the left. Move an available extension to the Installed list.
3. Click **OK**.

Remove an extension

1. In the Navigation pane, right-click a database and select **Manage Extensions**.
2. Move an installed extension to the Available list.
3. Click **OK**.

SQL Server

Databases & Schemas

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database and/or a new schema.

Create a new database

1. In the Navigation pane, right-click a connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Edit an existing database

1. In the Navigation pane, right-click a database and select **Edit Database**.

2. Edit the database properties in the pop-up window.


Create a new schema

1. In the Navigation pane, right-click a database and select **New Schema**.
2. Enter the schema properties in the pop-up window.

Edit an existing schema

1. In the Navigation pane, right-click a schema and select **Edit Schema**.
2. Edit the schema properties in the pop-up window.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

There are two ways to open a table with graphical fields, right-click a table and select:

Option	Description
Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the SHIFT key when right-clicking the table.)

You can create a table shortcut by right-clicking a table in the Objects tab and select **Create Open Table Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, right-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find** or pressing CTRL+F. When creating a new table, you are allowed to insert fields or rearrange the order of the fields.

Note: The tabs and options in the designer depend on the server version.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.





Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by right-clicking a view in the Objects tab and select **Create Open View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your view directly without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.


Button	Description
 Preview	Preview the data of the view.
 Explain	Show the Query Plan of the view.
 View Builder	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.

Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Procedures / Functions

Procedures and functions are schema objects that consist a set of SQL statements and stored in the server. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  **New Function** from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.

1. Specify the **Name** of the routine and select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Name**, **Type Schema**, **Type**, **Default Value**, **Output** and/or **Read Only** under the corresponding columns.
3. If you create a function, select the **Function Type** from the list. Then, choose the **Schema** and the **Return Type** if necessary.

4. Set the advanced options.







Hint: Once uncheck the **Show wizard next time** option, you can go to [Options](#) to enable it.

Function Designer


Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

The **Code Outline** pane displays information about the procedure/function including parameters, code body, etc. If the Code Outline pane is hidden, choose **View -> Code Outline**.

Note: Available only in Non-Essentials Edition.


Button	Description
	Refresh the code outline.
	Show the detail view of the code outline.
	Turn mouse over highlight on or off.
	Expand the selected item.
	Collapse the selected item.
	Toggle sorting by position.

Results

To execute the procedure/function, click  **Execute** on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the procedure/function requires input parameters, the **Input Parameter** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.

Note: Navicat supports to return 20 result sets.

Other Objects

Navicat also allows you to manage other SQL Server objects: Index, Synonym, Trigger, Backup Device, Linked Server, Server Trigger, Assembly, Database Trigger, Partition Function and Partition Scheme. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining SQL Server objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Right-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.

- Results show in a pop-up window.

Database

Option	Description
Read Write	Set the database to Read and Write mode.
Read Only	Set the database to Read Only mode.
Online	Bring the database online.
Offline	Take the database offline.
Emergency	Set the database to the Emergency state.
Multi User	Set the database to Multi User mode.
Single User	Set the database to Single User mode.
Restricted User	Set the database to Restricted User mode.

Assembly

Option	Description
Visible	Set the assembly to visible.
Invisible	Set the assembly to not visible.

Index

Option	Description
Rebuild	Rebuild and enable the index.
Reorganize	Reorganize the enabled index.
Disable	Disable the index.

Trigger / Database Trigger / Server Trigger

Option	Description
Enable	Enable the trigger.
Disable	Disable the trigger.

SQLite

Databases

To start working with the server objects, you should create and open a connection. The database file set in the General tab of the Connection window is named as the **main** database.

Attach a database file

- In the Navigation pane, right-click a connection and select **Attach Database**.
- Enter the database properties in the pop-up window.

Detach a database

1. In the Navigation pane, right-click an attached database and select **Detach Database**.

Encrypt main database

1. In the Navigation pane, right-click the main database and select **Encrypt Database**.
2. Enter the password in the pop-up window.


Decrypt main database

1. In the Navigation pane, right-click the main database and select **Decrypt Database**.
2. Confirm decrypting in the dialog window.

View the sqlite_master table

1. In the Navigation pane, right-click a database and select **View Master Table**.
2. The sqlite_master table opens in Table Viewer.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

You can create a table shortcut by right-clicking a table in the Objects tab and select **Create Open Table Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, right-click the selected table and select **Empty Table** from the pop-up menu.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find** or pressing CTRL+F.

Note: The tabs and options in the designer depend on the server version.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.





Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by right-clicking a view in the Objects tab and select **Create Open View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your view directly without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
 Preview	Preview the data of the view.
 Explain	Show the Query Plan of the view.
 View Builder	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.

Hint: You can choose to show the preview results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Other Objects

Navicat also allows you to manage other SQLite objects: Index and Trigger. In the main window, click the corresponding button from the main toolbar to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining SQLite objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Right-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Analyze Database	Collect statistics about the database.
Vacuum Database	Rebuild the database file. It only works on the main database.

Reindex Database	Delete and recreate all indexes within the database.
------------------	--

Table

Option	Description
Analyze Tables	Collect statistics about the contents of the table.
Reindex Tables	Delete and recreate all indexes of the table.
Get Rows Count	Count the number of rows in the table.

Index

Option	Description
Reindex	Delete and recreate the index.

MongoDB


Databases

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database.

Create a new database

1. In the Navigation pane, right-click your connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Collections

Collections are analogous to relational database tables for storing documents. In the main window, click  **Collection** to open the collection object list.

You can create a collection shortcut by right-clicking a collection in the Objects tab and select **Create Open Collection Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your collection for entering data directly without activating the Navicat main window.

To empty a collection, right-click the selected collection and select **Empty Collection** from the pop-up menu.

Collection Designer


Collection Designer is the basic Navicat tool for working with collections. It allows you to set the collection properties, indexes, validation, storage engine, and much more.

Note: The tabs and options in the designer depend on the server version.

Collection Viewer

When you open a collection, **Collection Viewer** displays data as a grid. Data can be displayed in three modes: Grid View, Tree View and JSON View. See [Data Viewer](#) for details.



Views

A view is the result of the applying the specified aggregation pipeline to the source collection or view. In the main window, click  **View** to open the view object list.

You can create a view shortcut by right-clicking a view in the Objects tab and select **Create Open View Shortcut** from the pop-up menu. This option is used to provide a convenient way for you to open your view directly without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views.

Button	Description
 Preview	Preview the data of the view.
 Explain	Show the Query Plan of the view.

In the **Pipeline** tab, you can add, insert or delete aggregation pipeline stages. In the **Operator** column, select an expression operator. An expression template will be generated in the **Expression** column, you can modify the template.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in three modes: Grid View, Tree View and JSON View. See [Data Viewer](#) for details.


Functions

You can store JavaScript functions for reuse. In the main window, click  **Function** to open the function object list.


Function Designer

Function Designer is the basic Navicat tool for working with functions. You can enter the function definition in the **Definition** tab. To customize the view of the editor and find out more features for script editing, see [Query Editor](#) for details.


Results

To execute the function, click  **Execute** on the toolbar. If the script is correct, the **Execute Function** dialog will pop up. Enter input parameters if necessary and click **OK**. If the function is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the function, execution stops, the appropriate error message is displayed.

Indexes

Navicat allows you to manage MongoDB indexes. In the main window, click  **Index** to open the index object list.





MapReduce

Map-Reduce is a data processing paradigm for condensing large volumes of data into useful aggregated results. In the main window, click  **MapReduce** to open the map-reduce object list.


You can set [automation tasks](#) to schedule Map-Reduce jobs.

Map-Reduce Designer


Map-Reduce Designer is the basic Navicat tool for working with Map-Reduce jobs.


Button	Description
 Run	Run the Map-Reduce job.
 Stop	Stop the running Map-Reduce job.
 Preview	Preview the documents by applying Input, Mapper, Reducer or Finalizer.
 Import Function	Import an existing function to Mapper, Reducer or Finalizer.

Results

To run the Map-Reduce job, click  **Run** on the toolbar. If you set to output the results inline, the **Result** tab opens with the documents returned, the number of documents and the timing information. If you set to write the results to a collection, the results return a document to the specified output collection.

GridFS





GridFS is a specification for storing and retrieving files. In the main window, click  **GridFS** to open the GridFS object list.




You can create multiple buckets in a database for storing files. Click  **New Bucket** and enter the name of the bucket.

To open the selected bucket, click  **Open Bucket**.

Bucket Viewer

Bucket Viewer is the basic Navicat tool for working with GridFS buckets. You can upload, download and view GridFS files that are inside the bucket.

Button	Description
 Open File	Open the selected GridFS file.
 Delete File	Delete the selected GridFS files.
 Upload File	Upload files into the bucket.
 Download File	Download the selected GridFS files.


 Filter	Filter the GridFS file table by creating and applying filter criteria.
 Preview	Preview an image file that is less than 1 MB.
 Progress	Check the status of file uploads and downloads.

File Table

The File table displays all the files that are uploaded to the bucket.



You can edit the GridFS file's name, content type, alias or metadata. In the table, right-click the name of the file and select **Modify File Name**, **Modify Content Type**, **Modify Alias** or **Modify Metadata**. Then, enter the information in the pop-up window.

Filter Pane

If you have many files uploaded to the bucket, you can find matching files using a filter. To toggle the Filter pane, click  **Filter**.

Progress Pane

The Progress pane displays the status of all file uploads and downloads in the current window. Parallel downloads and uploads are supported. If the window is closed, the list will be cleared.

When a file is starting to upload or download, click the corresponding buttons next to the progress bar to pause, resume and stop the process. After the process is finished, you can click  to open the folder that contains the file, or hover over an item and click  to remove it from the list.

If you want to pause, resume and stop all items that are in progress, right-click the list and select the appropriate options.

To clear the finished items, right-click the list and select **Clear All Finished**.

Maintain Objects

Navicat provides a complete solution for maintaining MongoDB objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Right-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Repair Database	Rebuild the database and indexes by discarding invalid or corrupt data.

Collection

Option	Description
Compact Collection	Rewrite and defragment all data and indexes in the collection.
Validate Collection	Check the structures within a namespace for correctness by scanning the collection's data and indexes.
Reindex Collection	Drop and recreate all indexes on the collection.

Redis

Databases

Redis supports 16 databases by default and databases are numbered from 0 to 15. Navicat lists all databases and the number of keys in each database when you connect to your Redis server. Simply double-click a database to open it.

Show / Hide empty databases

1. In the Navigation pane, right-click the connection and select **Show Empty Databases**.

Hint: You can configure Redis to support more databases by adjusting *databases* parameter value in the Redis configuration file (redis.conf). After setting, restart Redis to complete the configuration.

Data

All key-value data in a database is in a data view named **All Data**.

When you open All Data, the viewer displays data as a grid with key names, key types, key values, size and Time-to-Live (TTL). See [Data Viewer](#) for details.

Chapter 6 - Data Viewer

About Data Viewer

Navicat includes a data viewer that allows you to view, update, or delete data. The viewer also includes advanced features and editors that can help you understand the data as you manipulate it. You can use common keyboard navigation to browse your data.












RDBMS

RDBMS Data Viewer

RDBMS Data Viewer displays the data as a grid or a form. To switch the view, click  or  at the bottom.


Note: Form View is available only in Non-Essentials Edition.






The toolbar of the data viewer provides the following functions for managing data:













Button	Description
 Begin Transaction	Start a transaction. If Auto begin transaction is enabled in Options , transaction will be started automatically when opening the data viewer.
 Commit	Make permanent all changes performed in the current transaction.
 Rollback	Undo work done in the current transaction.
 Text	Activate the assistant editors for viewing and editing data.
 Filter	Filter records by creating and applying filter criteria for the data grid.
 Sort	Sort records by custom order.
 Columns	Show / Hide columns.
 Import	Import data from files.
 Export	Export data to files.
 Data Generation	Generate data for the table.
 Create Chart	Create a new Charts workspace with a data source using the table data.

Use Navigation Bar

Data Viewer provides a convenient way to navigate among the records/pages using the **Navigation Bar** buttons.



Button	Description
	Add Record - enter a new record. At any point when you are working in the data viewer, click on this button to get a blank display for a record.
	Delete Records - delete an existing record.
	Apply Changes - apply the changes.
	Discard Changes - remove all edits made to the current record.
	Refresh - refresh the data.

	Stop - stop when loading enormous data from server.
	First Page - move to the first page.
	Previous Page - move to the previous page.
	Next Page - move to the next page.
	Last Page - move to the last page.
	First Record - move to the first record.
	Previous Record - move one record back (if there is one) from the current record.
	Next Record - move one record ahead.
	Last Record - move to the last record.
	Limit Record Setting - set number of records showing on each page.
	Grid View - switch to Grid View.
	Form View - switch to Form View.

Use the **Limit Record Setting**  button to enter to the edit mode.

Limit records records per page

Check this option if you want to limit the number of records showed on each page. Otherwise, all records will be displayed in one single page. And, set the value in the edit box. The number representing the number of records showed per page.

Note: This setting mode will take effect on current object only. To adjust the global settings, see [Options](#).



Record a of b in page c

Display the numbers representing the selected record and page.

a - the selected record.

b - number of records in the current page.





c - the current page.

Edit Records


Grid View

Grid View is a spreadsheet-like view showing records and fields as rows and columns. The navigation bar allows you to switch the records quickly, insert or delete records.

To add a record

1. Make sure that your cursor is situated in the first blank cell on the table, then enter the desired data. If you are adding the new record into an existing table, just simply click on an existing record and click  from the navigation bar or press CTRL+N to get a blank display for a record.
2. Watch the graphics symbol in the record selectors box just to the left of your record. It will change from , which indicates that it is the current record, to , which indicates that you are editing this record.
3. Just simply move to another record to save the record or click  from the navigation bar.

To edit a record

1. Select the record that you wish to edit by clicking in the specific field you want to change.
2. Type in the new data for that field.
3. Just simply move to another record, the new data will overwrite the previous data or click  from the navigation bar.


Note: Close the table is another way to save the records.

To edit multiple cells with same data

1. Select a block of cells in the data grid.
2. Type in the new data.

Note: Changes will apply to multiple fields with compatible data type.



To delete a record

1. Select the record that you wish to delete.
2. Just simply right-click and select **Delete Record** or click  from the navigation bar.

Form View

Form View displays a single record at a time from a table. The navigation bar allows you to switch the records quickly, insert or delete records.

To add a record

1. Click  from the navigation bar or press CTRL+N to get a blank display for a record.
2. Enter the desired data.
3. Click  from the navigation bar to save the record.

To edit a record

1. Go to the record that you wish to edit.

2. Type in the new data for the specific field you want to change.
3. Click ✓ from the navigation bar. The new data will overwrite the previous data.

Note: Close the table is another way to save the records.

To delete a record




1. Go to the record that you wish to delete.
2. Just simply right-click and select **Delete Record** or click — from the navigation bar.

Edit Records with Special Handling

To set the cell value to an empty string or NULL, right-click the selected cell and select **Set to Empty String** or **Set to NULL**.

To view images in the grid, just simply choose **View -> Display -> Show Image In Grid**.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB.

id	image
1	
2	
3	

Hint: To view/edit images in an ease way, see [Image Editor](#).

To edit a Date/Time record, just simply click ... or press CTRL+ENTER to open the editor for editing. Choose/enter the desired data. The editor used in cell is determined by the field type assigned to the column.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB.


Date	Time	DateTime/Timestamp																																																																																																		
<div> <div> August 2021 </div> <table border="1"> <tr> <th>Sun</th><th>Mon</th><th>Tue</th><th>Wed</th><th>Thu</th><th>Fri</th><th>Sat</th></tr> <tr> <td>25</td><td>26</td><td>27</td><td>28</td><td>29</td><td>30</td><td>31</td></tr> <tr> <td>1</td><td>2</td><td>3</td><td>4</td><td>5</td><td>6</td><td>7</td></tr> <tr> <td>8</td><td>9</td><td>10</td><td>11</td><td>12</td><td>13</td><td>14</td></tr> <tr> <td>15</td><td>16</td><td>17</td><td>18</td><td>19</td><td>20</td><td>21</td></tr> <tr> <td>22</td><td>23</td><td>24</td><td>25</td><td>26</td><td>27</td><td>28</td></tr> <tr> <td>29</td><td>30</td><td>31</td><td>1</td><td>2</td><td>3</td><td>4</td></tr> </table> <div>Today: 6/28/2022</div> <div>OK Cancel</div> </div>	Sun	Mon	Tue	Wed	Thu	Fri	Sat	25	26	27	28	29	30	31	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	1	2	3	4	<div> 10:19:21 AM <div>OK Cancel</div> </div>	<div> <div> August 2021 </div> <table border="1"> <tr> <th>Sun</th><th>Mon</th><th>Tue</th><th>Wed</th><th>Thu</th><th>Fri</th><th>Sat</th></tr> <tr> <td>25</td><td>26</td><td>27</td><td>28</td><td>29</td><td>30</td><td>31</td></tr> <tr> <td>1</td><td>2</td><td>3</td><td>4</td><td>5</td><td>6</td><td>7</td></tr> <tr> <td>8</td><td>9</td><td>10</td><td>11</td><td>12</td><td>13</td><td>14</td></tr> <tr> <td>15</td><td>16</td><td>17</td><td>18</td><td>19</td><td>20</td><td>21</td></tr> <tr> <td>22</td><td>23</td><td>24</td><td>25</td><td>26</td><td>27</td><td>28</td></tr> <tr> <td>29</td><td>30</td><td>31</td><td>1</td><td>2</td><td>3</td><td>4</td></tr> </table> <div>Today: 6/28/2022</div> <div>10:19:27 AM</div> <div>OK Cancel</div> </div>	Sun	Mon	Tue	Wed	Thu	Fri	Sat	25	26	27	28	29	30	31	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	1	2	3	4
Sun	Mon	Tue	Wed	Thu	Fri	Sat																																																																																														
25	26	27	28	29	30	31																																																																																														
1	2	3	4	5	6	7																																																																																														
8	9	10	11	12	13	14																																																																																														
15	16	17	18	19	20	21																																																																																														
22	23	24	25	26	27	28																																																																																														
29	30	31	1	2	3	4																																																																																														
Sun	Mon	Tue	Wed	Thu	Fri	Sat																																																																																														
25	26	27	28	29	30	31																																																																																														
1	2	3	4	5	6	7																																																																																														
8	9	10	11	12	13	14																																																																																														
15	16	17	18	19	20	21																																																																																														
22	23	24	25	26	27	28																																																																																														
29	30	31	1	2	3	4																																																																																														

To edit an Enum record, just simply choose the record from the drop-down list.


Note: Available only for MySQL, PostgreSQL and MariaDB.

id	course
1	Maths
2	

- Chinese
- English
- Maths
- Music
- Sports

To edit a Set record, just simply click  or press CTRL+ENTER to open the editor for editing. Select the records from the list. To remove the records, uncheck them in the same way.

Note: Available only for MySQL and MariaDB.

id	course
1	English, Maths, Music, Sports
2	Apply Maths, Sports 

☐ Chinese
☐ English
☐ Maths
☐ Music
☒ Apply Maths
☒ Sports

To view BFile content, just simply choose **View -> Display -> Preview BFile**.


Note: Available only for Oracle.


To generate UUID/GUID, right-click the selected cell and select **Generate UUID**.

Note: Available only for PostgreSQL and SQL Server.

Edit Records with Foreign Key (Foreign Key Data Selection - Available only in Non-Essentials Edition)

Foreign Key Data Selection is a useful tool for letting you to get the available value from the reference table in an easy way. It allows you to show additional records from the reference table and search for particular records.


To include data to the record, just simply click  or press CTRL+ENTER to open the editor for editing.



Just simply double-click to select the desired data.


Hint: By default, the number of records showed is **1000**. To show all records, click . To refresh the records, click or press F5.

Click to open a pane on the left for showing a list of column names. Just simply click to show the additional column. To remove the columns, uncheck them in the same way.



Hint: To set column in ascending or descending mode, right-click anywhere on the column and select **Sort -> Sort Ascending / Sort Descending**.

Enter a search string into the **Filter** edit box and press ENTER to filter for the particular records.



Hint: To remove the filter results, simply remove the search string and press ENTER.

Copy Data from Grid View

Data that being copied from Navicat goes into the Windows clipboard with the fields delimited by tabs and the records delimited by carriage returns. It allows you to easily paste the clipboard contents into any application you want. Spreadsheet applications in general will notice the tab character between the fields and will neatly separate the clipboard data into rows and columns.

To select data using keyboard shortcuts

CTRL+A	Toggle the selection of all rows and columns in the data grid.
SHIFT+ARROW	Toggle the selection of cells as you move up/down/left/right in the data grid.

To select data using mouse actions

- Select the desired records by holding down the CTRL key while clicking on each row.
- Select range of records by clicking the first row you want to select and holding down the SHIFT key together with moving your cursor to the last row you wish to select.
- Select a block of cells.

Note: After you have selected the desired records, just simply press CTRL+C or right-click it and select **Copy**.

Paste Data into Grid View

Data are copied into the clipboard will be arranged as below format:

- Data are arranged into rows and column.
- Rows and columns are delimited by carriage returns/tab respectively.
- Columns in the clipboard have the same sequence as the columns in the data grid you have selected.

When pasting data into Navicat, you can replace the contents of current records and append the clipboard data into the table. To replace the contents of current records in a table, you must select the cells in the data grid whose contents must be replaced by the data in the clipboard. Just simply press CTRL+V or right-click and select **Paste** from the pop-up menu. Navicat will paste all the content in the clipboard into the selected cells. The paste action cannot be undone if you do not enable transaction.

Copy Records as Insert/Update Statements

To copy records as Insert/Update statement, right-click the selected records and select **Copy As -> Insert Statement** or **Update Statement**. Then, you can paste the statements in any editors.

Copy Field Name

To copy field names as tab separated values, right-click the selected columns/data and select **Copy As -> Tab Separated Values (Field Name only)**. If you want to copy data only or both field names and data, you can choose **Tab Separated Values (Data only)** or **Tab Separated Values (Field Name and Data)** respectively.

Save Data as a File

You can save the data in the table grid to a file. Simply right-click a cell and select **Save Data As**. Enter the file name and file extension in the Save As dialog.

Note: Not available when multiple selection.

Sort / Find / Replace Records


Sort Records

Server stores records in the order they were added to the table. Sorting in Navicat is used to temporarily rearrange records, so that you can view or update them in a different sequence.

Move over the column caption whose contents you want to sort by, click the right side of the column and select **Sort Ascending**, **Sort Descending** or **Remove Sort**.

payment_id	customer_id	staff_id	rental_id	amount
1				2.99
2				0.99
3				5.99
4				0.99
5	1	2	1476	9.99


To sort by custom order of multiple columns, click  **Sort** from the toolbar.



Find and Replace

Find Records

The Find bar is provided for quick searching for the text in the viewer. Just simply choose **Edit-> Find** or press CTRL+F. Then, choose **Find Data** and enter a search string. The search starts at the cursor's current position to the end of the file.




productCode	productName	productLine	productScale	productVendor
S10_1678	1969 Harley Davidson Ultra	Motorcycles	1:10	Min Lin Diecast
S10_1949	1952 Alpine Renault 1300	Classic Cars	1:10	Classic Metal
S10_2016	1996 Moto Guzzi 1100i	Motorcycles	1:10	Highway 66 Models
S10_4698	2003 Harley-Davidson Electra	Motorcycles	1:10	Red Start Diecast
S10_4757	1972 Alfa Romeo GTA	Classic Cars	1:10	Motor City Art
S10_4962	1962 Lancia Delta 16V	Classic Cars	1:10	Second Gear
S12_1099	1968 Ford Mustang	Classic Cars	1:12	Autoart Studio
S12_1108	2001 Ferrari Enzo	Classic Cars	1:12	Second Gear
S12_1666	1958 Setra Bus	Trucks and Buses	1:12	Welly Diecast
S12_2823	2002 Suzuki XREO	Motorcycles	1:12	Unimax Art
S12_3148	1969 Corvair Monza	Classic Cars	1:18	Welly Diecast
S12_3380	1968 Dodge Charger	Classic Cars	1:12	Welly Diecast
S12_3891	1969 Ford Falcon	Classic Cars	1:12	Second Gear
S12_3990	1970 Plymouth Hemi Cuda	Classic Cars	1:12	Studio M Art
S12_4473	1957 Chevy Pickup	Trucks and Buses	1:12	Exoto Design
S12_4675	1969 Dodge Charger	Classic Cars	1:12	Welly Diecast

To find for the next text, just simply click **Next** or press F3.

Replace Records

In the Find bar, check the **Replace** box and enter the text you want to search and replace. Click **Replace** or **Replace All** to replace the first occurrence or all occurrences automatically. If you clicked **Replace All**, you can click **Apply** to apply the changes or **Cancel** to cancel the changes.



Find Data: Moto	Next	Highlight All	<input checked="" type="checkbox"/> Replace
Wa	Replace	Replace All	

Find Fields

To search a field, just simply choose **Edit -> Find** or press CTRL+F. Then, choose **Find Field** and enter a search string.

products @classicmodels (Production Server 02) - Table

File Edit View Window Help

Begin Transaction Text Filter Sort Columns Import Export

productVendor	productDescription	quantityInStock	buyPrice	MSRP
Min Lin Diecast	This replica features work	7933	48.81	95.70
Classic Metal Creations	Turnable front wheels; ste	7305	98.58	214.30
Highway 66 Mini Classics	Official Moto Guzzi logo	6625	68.99	118.94
Red Start Diecast	Model features, official H	5582	91.02	193.66
Motor City Art Classics	Features include: Turnabl	3252	85.68	136.00
Second Gear Diecast	Features include: Turnabl	6791	103.42	147.74
Autoart Studio Design	Hood, doors and trunk al	68	95.34	194.57
Second Gear Diecast	Turnable front wheels; ste	3619	95.59	207.80
Welly Diecast Production	Model features 30 windo	1579	77.90	136.67
Unimax Art Galleries	Official logos and insigni	9997	66.27	150.62
Welly Diecast Production	1:18 scale die-cast about	6906	89.14	151.08
Welly Diecast Production	1:12 scale model of a 19t	9123	75.16	117.44
Second Gear Diecast	Turnable front wheels; ste	1049	83.05	173.02
Studio M Art Models	Very detailed 1970 Plymc	5663	31.92	79.80
Exoto Designs	1:12 scale die-cast about	6125	55.70	118.50
Welly Diecast Production	Detailed model of the 19	7323	58.73	115.16

Find Field: product Next Highlight All


SELECT * FROM 'classicmodels'.products LIMIT 0,1 Record 1 of 110 in page 1

There are some additional options for Find and Replace, click :

Option	Description
Highlight All	Highlight all matches in the viewer.
Incremental Search	Find matched text for the search string as each character is typed.
Match Case	Enable case sensitive search.

Filter Records

Use either of the following methods to filter the data in the grid:

- Right-click a cell and select **Filter** -> **Field xxx Value** from the pop-up menu to filter records by the current value in the cell.
- The **Custom Filter** dialog is provided for quick building a simple filter. Just simply right-click the grid and select **Filter** -> **Custom Filter** from the pop-up menu. Use character '_' to represent any single symbol in the condition and use character '%' to represent any series of symbols in the condition.
- You can also customize your filter in a more complicated way by right-clicking a field and selecting **Filter** -> **Filter** from the pop-up menu or clicking  **Filter** from the toolbar. The Filter Wizard becomes visible at the top of the grid, where you can see the active filtering condition and easily enable or disable it by clicking a check box at the left.

Manipulate Raw Data

Navicat normally recognize what user has input in a table as normal string, any special characters or functions would be processed as plain text (that is, its functionality would be skipped).

Editing data in **Raw Mode** provides an ease and direct method to apply server built-in functions. To access Raw Mode, just simply choose **View -> Display -> Raw Mode**.

Note: Available only for MySQL, PostgreSQL, SQLite, SQL Server and MariaDB.

JOB_ID	JOB_TITLE	MIN_SALARY
'AC_ACCOUNT'	'Public Accountant'	4200
'AC_MGR'	'Accounting Manager'	8200
'AD_ASST'	CONCAT('Administration',' ', 'Assistant')	3000
'AD_PRES'	'President'	20000
'AD_VP'	'Administration Vice President'	15000

Format Data View

Use the following methods to format the table:

Hint: Form View only supports Show/Hide Columns.

Move Columns

1. Click on the column header and hold down the left mouse button.
2. Move the pointer until a double black line appears in the desired location.
3. Release the mouse and the column will move.

JOB_ID	MIN_SALARY	JOB_TITLE	MAX_SALARY
AC_MGR	8200	Accounting Manager	16000
AD_ASST	3000	Administration Assistant	6000
AD_PRES	20000	President	40000
AD_VP	15000	Administration Vice President	30000
FI_ACCOUNT	4200	Accountant	9000
FI_MGR	8200	Finance Manager	16000
HR_REP	4000	Human Resources Representative	9000

Freeze Selected Column

If there are many columns in the table and you want to freeze one or more columns to identify the record, just simply right-click the column you want to freeze and select **Display -> Freeze Selected Column** or select from the **View** menu.

The frozen columns will move to the leftmost position in the table grid. This action will lock the frozen columns, preventing them from being edited.

To unfreeze the columns, just simply right-click anywhere on the table grid and select **Display -> Unfreeze Columns** or select from the **View** menu.

Set Column Width

- Click right border at top of column and drag either left or right.
- Double-click right border at top of column to obtain the best fit for the column.
- Right-click the column you want to set the column width with and select **Display -> Set Column Width** or select from the **View** menu. Specify width in the **Set Column Width** dialog.


Hint: The result only applies on the selected column.

Set Row Height

Right-click anywhere on the table grid and select **Display -> Set Row Height** or select from the **View** menu. Specify row height in the **Set Row Height** dialog.

Hint: This action applies on the current table grid only.

Show/Hide Columns

If there are many columns in the table and you want to hide some of them from the grid/form, just simply click  **Columns**. Select the columns that you would like to hide.

The hidden columns will disappear from the grid/form.

To unhide the columns, just simply click  **Columns**. Select the columns that you would like to redisplay.

<input checked="" type="checkbox"/> customer_id	customer_id	store_id	address_id	active
<input checked="" type="checkbox"/> store_id	1	2	5	1
<input type="checkbox"/> first_name	2	1	6	1
<input type="checkbox"/> last_name	3	1	7	1
<input type="checkbox"/> email	4	2	8	1
<input checked="" type="checkbox"/> address_id	5	1	9	1
<input checked="" type="checkbox"/> active	6	2	10	1
<input type="checkbox"/> create_date				
<input type="checkbox"/> last_update				

Show/Hide ROWID

If you want to display or hide the rowid (address) of every row, right-click anywhere on the table grid and select **Display -> Show/Hide ROWID** or select from the **View** menu.

The ROWID column will be showed in the last column.

Note: Available only for Oracle and SQLite.

View Field Comments




If you have added comments to the table fields, you can hover mouse over the column caption to view the comment. Field comments are displayed as tooltips.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB.















address_id	active	create_date	last_update
5	1	2006-02-14 22:04:36	2006-02-15 00:00:00
6	1	2006-02-14 22:04:36	2006-02-15 00:00:00
7	1	2006-02-14 22:04:36	2017-07-28 10:00:00
8	1	2006-02-14 22:04:36	2017-07-28 10:00:00

MongoDB

MongoDB Data Viewer


MongoDB Data Viewer displays the data as a grid or a tree, or in JSON format. To switch the view, click ,  or  at the bottom.

The toolbar of the data viewer provides the following functions for managing data:













Button	Description
 Begin Transaction	Start a transaction. If Auto begin transaction is enabled in Options , transaction will be started automatically when opening the data viewer.
 Commit	Make permanent all changes performed in the current transaction.
 Rollback	Undo work done in the current transaction.
 Text	Activate the assistant editors for viewing and editing data. Available only for Grid View and Tree View.
 Filter	Filter records by creating and applying filter criteria for the data grid.
 Sort	Sort records by custom order.
 Columns	Show / Hide columns.
 Expand All	[Tree View] Expand all embedded documents and arrays.
 Collapse All	[Grid View] Collapse all embedded documents. [Tree View] Collapse all embedded documents and arrays.
 Type Color	[Grid View] Use the specified type color set on the Type Color pane to highlight cells.
 Import	Import data from files.
 Export	Export data to files.
 Analyze	Analyze the collection.
 Data Generation	Generate data for the collection.

Use Navigation Bar

Data Viewer provides a convenient way to navigate among the documents/pages using the **Navigation Bar** buttons.



Button	Description
+	Add Document - enter a new document. At any point when you are working in the data viewer, click on this button to get a blank display for a document.
-	Delete Documents - delete an existing document.
✓	Apply Changes - apply the changes.
✗	Discard Changes - remove all edits made to the current document.
↻	Refresh - refresh the data.
■	Stop - stop when loading enormous data from server.


	First Page - move to the first page.
	Previous Page - move to the previous page.
	Next Page - move to the next page.
	Last Page - move to the last page.
	First Document - move to the first document.
	Previous Document - move one document back (if there is one) from the current document.
	Next Document - move one document ahead.
	Last Document - move to the last document.
	Limit Document Setting - set number of documents showing on each page.
	Grid View - switch to Grid View.
	Tree View - switch to Tree View.
	JSON View - switch to JSON view.

Use the **Limit Document Setting**  button to enter to the edit mode.

Limit documents **documents per page**

Check this option if you want to limit the number of documents showed on each page. Otherwise, all documents will be displayed in one single page. And, set the value in the edit box. The number representing the number of documents showed per page.

Note: This setting mode will take effect on current object only. To adjust the global settings, see [Options](#).



Document a of b in page c

Display the numbers representing the selected document and page.

a - the selected document.


b - number of documents in the current page.




c - the current page.

Grid View

Grid View is a spreadsheet-like view showing documents and fields as rows and columns. The navigation bar allows you to switch the documents quickly, insert or delete documents.

To add a document using the grid

1. Click on an existing document and click  from the navigation bar or press CTRL+N to get a blank display for a document.
2. Enter the desired data.


3. Watch the graphics symbol in the document selectors box just to the left of your document. It will change from , which indicates that it is the current document, to , which indicates that you are editing this document.
4. Just simply move to another document to save the document or click  from the navigation bar.

Note: If your collection is empty, a window will pop up for you to add documents.

To add a document using the pop-up window

1. Right-click the grid and select **Add Document**.
2. Write the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Add**.

To edit a document using the grid

1. Select the document that you wish to edit by clicking in the specific cell you want to change.
2. Type in the new data for that cell.
3. Just simply move to another document or click  from the navigation bar, the new data will overwrite the previous data.

To edit a document using the pop-up window

1. Right-click the document that you wish to edit and select **Edit Document**.
2. Edit the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Update**.

Note: Close the collection is another way to save the documents.

To edit multiple cells with same data

1. Select a block of cells in the data grid.
2. Type in the new data.

Note: Changes will apply to multiple cells with compatible data type.

To delete a document


1. Select the document that you wish to delete.

2. Just simply right-click and select **Delete Document** or click  from the navigation bar.

Edit Documents with Special Handling

To set the cell value to an empty string or NULL, right-click the selected cell and select **Set to Empty String** or **Set to NULL**.

To edit a DateTime data, just simply click  or press CTRL+ENTER to open the editor for editing. Choose/enter the desired data.



To change the type of a cell value, right-click the selected cell and select **Value Type**. Then, select the desired type.

Copy Data from Navicat

Data that being copied from Navicat goes into the Windows clipboard with the fields delimited by tabs and the documents delimited by carriage returns. It allows you to easily paste the clipboard contents into any application you want. Spreadsheet applications in general will notice the tab character between the fields and will neatly separate the clipboard data into rows and columns.

To select data using keyboard shortcuts

CTRL+A	Toggle the selection of all rows and columns in the data grid.
SHIFT+ARROW	Toggle the selection of cells as you move up/down/left/right in the data grid.

To select data using mouse actions

- Select the desired documents by holding down the CTRL key while clicking on each row.
- Select range of documents by clicking the first row you want to select and holding down the SHIFT key together with moving your cursor to the last row you wish to select.
- Select a block of cells.

Note: After you have selected the desired documents, just simply press CTRL+C or right-click it and select **Copy**.

Paste Data into Navicat

Data are copied into the clipboard will be arranged as below format:

- Data are arranged into rows and column.

- Rows and columns are delimited by carriage returns/tab respectively.
- Columns in the clipboard have the same sequence as the columns in the data grid you have selected.

When pasting data into Navicat, you can replace the contents of current documents and append the clipboard data into the collection. To replace the contents of current documents in a collection, you must select the cells in the data grid whose contents must be replaced by the data in the clipboard. Just simply press CTRL+V or right-click and select **Paste** from the pop-up menu. Navicat will paste all the content in the clipboard into the selected cells. The paste action cannot be undone if you do not enable transaction.

Copy Field Name

To copy field names as tab separated values, right-click the selected fields/documents and select **Copy As -> Tab Separated Values (Field Name only)**. If you want to copy data only or both field names and data, you can choose **Tab Separated Values (Data only)** or **Tab Separated Values (Field Name and Data)** respectively.


Save Data as a File

You can save the data in the grid to a file. Simply right-click a cell and select **Save Data As**. Enter the file name and file extension in the Save As dialog.

Note: Not available when multiple selection.

Filter Documents


Use either of the following methods to filter the data in the grid:


- Right-click a cell and select **Filter -> Field xxx Value** from the pop-up menu to filter documents by the current value of the selected field.
- The **Custom Filter** dialog is provided for quick building a simple filter. Just simply right-click the grid and select **Filter -> Custom Filter** from the pop-up menu. Enter a projection or a query likes: { field1: <value>, field2: <value> ... }.
- You can also customize your filter in a more complicated way by right-clicking a field and selecting **Filter -> Filter** from the pop-up menu or clicking  **Filter** from the toolbar. The Filter Wizard becomes visible at the top of the grid, where you can see the active filtering condition and easily enable or disable it by clicking a check box at the left.


Format Grid View

Use the following methods to format the collection grid:



Highlight Cells based on Types


Grid View allows highlighting cells based on data types to make particular cells easy to identify. The Type Color pane is on the right side of the grid. If the grid window is docked to the Navicat main window, you can click the  icon in the Information pane to set the color.

To apply the color, click the  **Type Color** button on the toolbar or check the **Enable Coloring** option on the Type Color pane.





Expand/Collapse Embedded Documents

Grid View allows embedded documents to be expanded alongside other columns for easier data analysis. To expand or collapse an embedded document, just simply click on the cell with embedded document and click  or , or right-click the cell and select **Expand**, **Collapse** or **Collapse All Embedded Documents**.


60	IT	103
70	Public Relations	204
80	Sales	145
90	(Document) 2 Fields 	(Array) 3 Elements
100	Finance	108
110	Accounting	205
120	Treasury	205

Expand Arrays

Grid View allows showing all elements in an array. To expand array elements, just simply click on the cell with array elements and click , or right-click the cell with array elements and select **Expand**.

IT	103	1400
Public Relations	204	2700
Sales	145	2500
(Document) 2 Fields	(Array) 3 Elements 	1700
Finance	108	1700
Accounting	205	1700
Treasury	205	1700

All array elements display on a new grid. You can view, add or delete the elements here. Click the collection name to jump back to the collection grid.



Move Columns

1. Click on the column header and hold down the left mouse button.
2. Move the pointer until a double black line appears in the desired location.
3. Release the mouse and the column will move.

_id	DEPARTMENT_ID	DEPARTMENT_NAME	MANAGER_ID
5b3c34124348b20a10003a8e	10	Administration	200
5b3c34124348b20a10003a8f	20	Marketing	201
5b3c34124348b20a10003a90	30	Purchasing	114
5b3c34124348b20a10003a91	40	Human Resources	203
5b3c34124348b20a10003a92	50	Shipping	121
5b3c34124348b20a10003a93	60	IT	103
5b3c34124348b20a10003a94	70	Public Relations	204
5b3c34124348b20a10003a95	80	Sales	145
5b3c34124348b20a10003a96	90	(Document) 2 Fields	100

Freeze Selected Column

If there are many columns in the collection and you want to freeze one or more columns to identify the document, just simply right-click the column you want to freeze and select **Display-> Freeze Selected Column** or select from the **View** menu.

The frozen columns will move to the leftmost position in the collection grid. This action will lock the frozen columns, preventing them from being edited.

To unfreeze the columns, just simply right-click anywhere on the collection grid and select **Display -> Unfreeze Columns** or select from the **View** menu.

Set Column Width

1. Click right border at top of column and drag either left or right.
2. Double-click right border at top of column to obtain the best fit for the column.
3. Right-click the column you want to set the column width with and select **Display -> Set Column Width** or select from the **View** menu. Specify width in the **Set Column Width** dialog.


Hint: The result only applies on the selected column.

Set Row Height


Right-click anywhere on the collection grid and select **Display -> Set Row Height** or select from the **View** menu. Specify row height in the **Set Row Height** dialog.

Hint: This action applies on the current collection grid only.

Show/Hide Columns

If there are many columns in the collection and you want to hide some of them from the collection grid, just simply click  **Columns**. Select the columns that you would like to hide.

The hidden columns will disappear from the collection grid.



To unhide the columns, just simply click  **Columns**. Select the columns that you would like to redisplay.


<input type="checkbox"/> .id	EMPLOYEE_ID	JOB_ID	MANAGER_ID
<input checked="" type="checkbox"/> EMPLOYEE_ID	100	AD_PRES	(Null)
<input type="checkbox"/> FIRST_NAME	101	AD_VP	100
<input type="checkbox"/> LAST_NAME	102	AD_VP	100
<input type="checkbox"/> EMAIL	103	IT_PROG	102
<input type="checkbox"/> PHONE_NUMBER	104	IT_PROG	103
<input type="checkbox"/> HIRE_DATE	105	IT_PROG	103
<input checked="" type="checkbox"/> JOB_ID	106	IT_PROG	103
<input type="checkbox"/> SALARY			
<input type="checkbox"/> COMMISSION_PCT			
<input checked="" type="checkbox"/> MANAGER_ID			

Tree View


Tree View displays documents in a hierarchical view. The navigation bar allows you to switch the documents quickly, insert or delete documents.

To add a document


1. Click  from the navigation bar or press CTRL+N to get a blank display for a document.
2. Enter the desired data.
3. Click  from the navigation bar to save the document .

Note: If your collection is empty, you need to click  to add a new field.

To edit a document

1. Go to the document that you wish to edit.
2. Click on a field name, a value or a type to modify.
3. Click  from the navigation bar to apply the changes.

To add a field or an item


1. Go to the document that you wish to edit.
2. Click  to add a new field/item.
3. Enter the desired data.

To delete a field or an item

1. Go to the document that you wish to edit.
2. Right-click the field/item you want to delete and select **Delete Value**.


Note: Close the collection is another way to save the documents.


To delete a document

1. Go to the document that you wish to delete.
2. Just simply click  from the navigation bar.

Edit Documents with Special Handling

To set the value to an empty string or NULL, right-click the selected item and select **Set to Empty String** or **Set to NULL**.

To edit a DateTime data, just simply click  to open the editor for editing. Choose/enter the desired data.



Format Tree View

Expand/Collapse Embedded Documents & Arrays

All embedded Documents and arrays are represented as nodes. The nodes can be expanded or collapsed by clicking the node icon.

<code>_id</code> : 5d8c74417e6b0000040014fb	Object ID
<code>DEPARTMENT_ID</code> : 90	Int32
▼ <code>DEPARTMENT_NAME</code> : (Document) 2 Fields	Document
<code>NAME1</code> : CS	String
<code>NAME2</code> : IT Support	String
+	
▼ <code>MANAGER_ID</code> : (Array) 3 Elements	Array
0: 101	Int32
1: 103	Int32
2: 105	Int32
+	
<code>LOCATION_ID</code> : 1700	Double
+	

JSON View

JSON View displays documents in JSON format. The navigation bar allows you to switch the documents quickly, insert or delete documents.

To add a document

1. Click **+** from the navigation bar or press CTRL+N.
2. Write the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Add**.

To edit a document

1. Right-click the document that you wish to edit and select **Edit Document**.
2. Edit the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Update**.

To delete a document

1. Click on the document that you wish to delete.
2. Just simply click **—** from the navigation bar.

Sort / Find / Replace Documents

Sort Documents

Server stores documents in the order they were added to the collection. Sorting in Navicat is used to temporarily rearrange documents, so that you can view or update them in a different sequence.

Move over the field caption whose contents you want to sort by, click the right side of the field and select **Sort Ascending**, **Sort Descending** or **Remove Sort**.

FIRST_NAME	LAST_NAME	EMAIL	PHONE_NUMBER
Steven	King	Sort Ascending	567
Neena	Kochhar	Sort Descending	568
Lex	De Haan	Remove Sort	569
Alexander	Hunold		567
Bruce	Ernst	BERNST	590.423.4568

To sort by custom order of multiple fields, click  **Sort** from the toolbar.

employees @hr (MongoDB) - Collection

File Edit View Window Help

Begin Transaction Text Filter Sort Columns Collapse All Type Color

☒ JOB_ID ASC
☒ SALARY DESC

↑ ↓ ✓ Apply

HIRE_DATE	JOB_ID	SALARY	COMMISSION_PCT	MANAGER_ID
1994-06-07 00:00:00.000	AC_ACCOUNT	8300	(Null)	205
1994-06-07 00:00:00.000	AC_MGR	12000	(Null)	101
1987-09-17 00:00:00.000	AD_ASST	4400	(Null)	101
1987-06-17 00:00:00.000	AD_PRES	24000	(Null)	(Null)
1989-09-21 00:00:00.000	AD_VP	17000	(Null)	100
1993-01-13 00:00:00.000	AD_VP	17000	(Null)	100
1994-08-16 00:00:00.000	FI_ACCOUNT	9000	(Null)	108
1997-09-28 00:00:00.000	FI_ACCOUNT	8200	(Null)	108
1998-03-07 00:00:00.000	FI_ACCOUNT	7800	(Null)	108
1997-09-30 00:00:00.000	FI_ACCOUNT	7700	(Null)	108
1999-12-07 00:00:00.000	FI_ACCOUNT	6900	(Null)	108
1994-08-17 00:00:00.000	FI_MGR	12000	(Null)	101
1994-06-07 00:00:00.000	HR_REP	6500	(Null)	101
1990-01-03 00:00:00.000	IT_PROG	9000	(Null)	102

db.getCollection("employees").f DateTime Document 1 of 107 in page 1

Find and Replace

Find Documents

The Find bar is provided for quick searching for the text in the viewer. Just simply choose **Edit-> Find** or press CTRL+F. Then, enter a search string. The search starts at the cursor's current position to the end of the file.

For Grid View or Tree View, you need to choose **Find Data** or **Find Value**.

employees @hr (MongoDB) - Collection

File Edit View Window Help

Begin Transaction Text Filter Sort Columns Collapse All Type Color

_id	EMPLOYEE_ID	FIRST_NAME	LAST_NAME	EMAIL	PH
5db2adeb0b4cbe39ac2:	113	Luis	Popp	LPOPP	515
5db2adeb0b4cbe39ac2:	114	Den	Raphaely	DRAPHEAL	515
5db2adeb0b4cbe39ac2:	115	Alexander	Khoo	AKHOO	515
5db2adeb0b4cbe39ac2:	116	Shelli	Baida	SBAIDA	515
5db2adeb0b4cbe39ac2:	117	Sigal	Tobias	STOBIAS	515
5db2adeb0b4cbe39ac2:	118	Guy	Himuro	GHIMURO	515
5db2adeb0b4cbe39ac2:	119	Karen	Colmenares	KCOLMENA	515
5db2adeb0b4cbe39ac2:	120	Matthew	Weiss	MWEISS	650
5db2adeb0b4cbe39ac2:	121	Adam	Fripp	AFRIPP	650
5db2adeb0b4cbe39ac2:	122	Payam	Kaufling	PKAUFLIN	650
5db2adeb0b4cbe39ac2:	123	Shanta	Vollman	SVOLLMAN	650
5db2adeb0b4cbe39ac2:	124	Kevin	Mourgos	KMOURGOS	650
5db2adeb0b4cbe39ac2:	125	Julia	Nayer	JNAYER	650
5db2adeb0b4cbe39ac2:	126	Irene	Mikkilineni	IMIKKILI	650
5db2adeb0b4cbe39ac2:	127	James	Landry	JLANDRY	650
5db2adeb0b4cbe39ac2:	128	Steven	Markle	SMARKLE	650
5db2adeb0b4cbe39ac2:	129	Laura	Bissot	LBISSOT	650


Find Data: Sh Next Highlight All Replace

db.getCollection("employees").f String Document 17 of 107 in page 1

To find for the next text, just simply click **Next** or press F3.


Replace Documents

In the Find bar, check the **Replace** box and enter the text you want to search and replace. Click **Replace** or **Replace All** to replace the first occurrence or all occurrences automatically. If you clicked **Replace All**, you can click **Apply** to apply the changes or **Cancel** to cancel the changes.



Find Fields

In Grid View or Tree View, you can search for fields in the collection. Just simply choose **Edit -> Find** or press CTRL+F. Then, choose **Find Field** and enter a search string.



There are some additional options for Find and Replace, click :





Option	Description
Highlight All	Highlight all matches in the viewer.
Incremental Search	Find matched text for the search string as each character is typed.
Match Case	Enable case sensitive search.

Redis

Redis Data Viewer


Navicat lets you explore keys in your Redis server using a spreadsheet-like data grid. You can add, edit and delete a key, even update the key expiry using the editor.





The toolbar of the data viewer provides the following functions for managing data:

Button	Description
 Save Profile	Create a profile with the current view of the key data.
 Flatten	Toggle between list view or tree view of keys.
 Editor	Activate the assistant editor for viewing and editing data.
 Search	Search for keys using a string or a key pattern.

Use Navigation Bar

Data Viewer provides a convenient way to navigate among the keys using the **Navigation Bar** buttons.




Button	Description
+	Add Key - enter a new key. At any point when you are working in the data viewer, click on this button to get a blank display for a key.
—	Delete Keys - delete an existing key.
Last Refresh	Last Refresh - display the last refresh date and time or the elapsed time since the last refresh.
 Refresh	Refresh - refresh the data.
 Fetch More	Fetch More - fetch the next batch size of keys.
 Fetch All	Fetch All - fetch all remaining keys.
	Batch Size Settings - set number of keys showing when opening the data view.

Use the **Batch Size Settings**  button to enter to the edit mode.

Batch Size



Set the value in the edit box. The number representing the number of keys fetched from the server.

Note: This setting mode will take effect on current data view only.




Edit Keys

Data View is a spreadsheet-like view showing keys as rows and columns. The navigation bar allows you to insert or delete keys.

By default, when opening the data viewer, Navicat loads the number of keys in batch size. If you want to fetch more keys, you can click  **Fetch More** or  **Fetch All**.

Hint: Newly fetched keys are marked with green indicators. You can unmark them by right-clicking on the grid and selecting **Unmark All Indicators**.

To add a key


1. Click  from the navigation bar or press CTRL+N to get a blank display for a key.
2. Enter the key properties using the **Editor**.
3. Just simply move to another key to save the key or click **Apply**.

To edit a key

1. Double-click the key that you wish to edit.
2. Type in the new data using the **Editor**.
3. Just simply move to another key or click **Apply**, the new data will overwrite the previous data.

Hint: You can modify key names, key types, key values and time to live (TTL).

To delete a key

1. Select the key that you wish to delete.
2. Just simply right-click and select **Delete Key** or click  from the navigation bar.

Hint: You can hold down the SHIFT or CTRL key and click to select multiple keys at a time.


Sort Keys


By default, the data grid displays keys in ascending order by key name. Sorting in Navicat is used to temporarily rearrange keys, so that you can view or update them in a different sequence.

Click the column caption whose contents you want to sort by and select **Sort Asc**, **Sort Desc** or **Remove Sort**.

Key ^	Type	Value	Size
Aaron Eckhart	hash	[first_u, date_of_birth:1968]	120 B
Aaron Paul	hash	[first_u, te_of_birth:1979]	120 B
Aaron Taylor-Johnson	hash	[first_u, ohnson, date_of_birth:1...	144 B
Abbey Lee	hash	[first_u, te_of_birth:1987]	120 B
> actor (452)			


Search Keys

The Search feature is provided for quick searching for keys in the database. Just simply enter a key name in the **Search** box and click  **Search** or press ENTER.








There are some additional options for Search, click :

Option	Description
Keys Contain	Return all keys contains the search string (case insensitive).
Keys Contain (Match Case)	Enable case sensitive search.
Keys Match Pattern	Return all keys matching the pattern.


To remove the search, just simply click  **Clear Search**.


Assistant Editors

Navicat provides powerful assistant editors to view and edit fields content. The editor allows you to view, update, insert, or delete data in a table or a collection. Click  **Text**,  **Hex**,  **Image**,  **Web** or  **Editor** from the toolbar to activate the appropriate viewer/editor.




Note: Oracle BFile fields cannot be edited. MongoDB JSON View does not support assistant editors.

MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB, MongoDB

The **Text** pane allows you to edit data as a simple text. To change the syntax highlight, simply right-click the empty space and select **Language**. Use the  button on the navigation bar to update the changed records or documents.

The **Hex** pane allows you to edit data in hexadecimal mode. Use the  button on the navigation bar to update the changed records or documents.

Note: Use the INSERT key on the keyboard to switch between Insert and Overwrite modes.


The **Image** pane allows you to show data as image. Use the  **Load**,  **Save to disk** and  **Clear** buttons to load/remove the image from a file, and save the image to a file.

The **Web** pane allows you to show data with HTML codes as in a web browser.


Redis

The **Editor** pane allows you to edit the key's name, type, value and TTL. Use the **Apply** button to update the changes.



Filter Wizard

Filter Wizard allows you to facilitate creating and applying filter criteria that you specify for the data grid. Moreover, it allows you to save filter criteria as a profile for future use. Click  **Filter** from the toolbar to activate the filter.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.



Create Filter

1. To add a new condition to the criteria, just simply click . If you want to add a condition with parentheses, click .

Hint: To add parentheses to existing conditions, simply right-click on the selected conditions and select **Group with Bracket**. To remove the parentheses, right-click a bracket and select **Delete Bracket** or **Delete Bracket and Conditions**.


2. Click on the field name (next to the checkbox) and choose a field from the list.
3. Click on the operator (next to the field name) and choose a filter operator. You can choose **[Custom]** from the list to enter the condition manually.

Filter Operator	Operator Description
=	The field is equal to 'value'.
!=	The field is not equal to 'value'.
<	The field is less than 'value'.
<=	The field is less than or equal to 'value'.
>	The field is greater than 'value'.

>=	The field is greater than or equal to 'value'.
contains	The field contains 'value'.
contains (case insensitive)	The field contains 'value' (case insensitive). Available only for PostgreSQL.
does not contain	The field does not contain 'value'.
does not contain (case insensitive)	The field does not contain 'value' (case insensitive). Available only for PostgreSQL.
begin with	The field starts with 'value'.
does not begin with	The field does not start with 'value'.
end with	The field ends with 'value'.
does not end with	The field does not end with 'value'.
is null	The field is NULL.
is not null	The field is NOT NULL.
is empty	The field is empty.
is not empty	The field is not empty.
is between	The field is between 'value1' and 'value2'.
is not between	The field is not between 'value1' and 'value2'.
is in list	The field is in the list of ('value1','value2',...).
is not in list	The field is not in the list of ('value1','value2',...).
exists	The field exists. Available only for MongoDB.
does not exist	The field does not exist. Available only for MongoDB.
is field type	The field type is 'value'. Available only for MongoDB.
is not field type	The field type is not 'value'. Available only for MongoDB.

- Click on **<?>** to activate the appropriate editor and enter the criteria values. The editor used in the criteria values box is determined by the data type assigned to the corresponding field.

Hint: For MongoDB, you can change the editor type in the criteria values box.

- Click on the logical operator (next to the criteria values) to choose **and** or **or**.
- Repeat step 1-5 to add another new condition.
- Click  to see the result of the filtering you made.



Hint: If you want to reverse the meaning of the conditions, right-click the selected conditions and select **Toggle Negator**. (Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB)

[Save Profile](#)

You are allowed to save filter criteria to profiles for future use. Just simply right-click on the Filter Wizard and select **Load Profile, Delete Profile, Save Profile** or **Save Profile As**.

Chapter 7 - Query

About Query














A query is used to extract data from the database in a readable format according to the user's request. Navicat provides powerful tools for working with queries: Query Editor for editing the query text directly, and Query Builder, Find Builder or Aggregate Builder for building queries visually. You can save your queries for setting [automation tasks](#). In the main window, click  **Query** to open the query object list. You can also click  **New Query** in the main toolbar to create a new query without opening any connections.

To open a query using an external editor, right-click it and select **Open with External Editor**. You can set the file path of an external editor in [Options](#).

Hint: Queries (.sql, .js or .redis) are stored under the [Settings Location](#). To open the folder, right-click a query and select **Open Containing Folder**. If the connection is synchronized to [Navicat Cloud](#) or [On-Prem Server](#), its queries will be stored in the cloud.

Query Designer

Query Designer is the basic Navicat tool for working with queries.

Button	Description
MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB	
 Query Builder	Open the Query Builder for building queries visually.
 Beautify SQL	Format the codes with the Beautify SQL settings in Editor.
 Create Chart	Create a new Charts workspace with a data source using the query.
MongoDB	
 Find Builder	Open the Find Builder for building queries visually.
 Aggregate Builder	Open the Aggregate Builder for building queries visually.
 Beautify Script	Format the codes in Editor.
 Type Color	[Grid View] Use the specified type color set on the Type Color pane to highlight cells.
Common	
 Code Snippet	Show the Code Snippet pane.
 Text	Activate the assistant editors for viewing and editing data.
 Export Result	Export the result of the query.
 Run	Execute the query: Run, Run Current Statement, or Run Selected (when highlighted code). MongoDB does not support Run Current Statement.
 Stop	Stop the executing query.
 Explain	Show the Query Plan of the query: Explain or Explain Selected (when highlighted code).

Open an external file in Navicat

1. In the menu bar, choose **File -> Open External File -> Query**.
2. Select the file and choose the encoding.
3. Click **Open**.

Save an opened external file as a Navicat query

1. In Query Designer, choose **File -> Save to Navicat**.
2. Enter the query name and choose the save location.
3. Click **OK**.

Save a Navicat query as an external file

1. In Query Designer, choose **File -> Save As External File**.
2. Choose the save path and enter the file name.
3. Click **Save**.

RDBMS

Query Editor

SQL Editor allows you to create and edit SQL text, prepare and execute selected queries. You can define multiple SQL statements in one query window. Drag-and-drop or double-click an identifier in the right **Identifiers** pane to add it to the editor.

Hint: SELECT statement will be automatically generated in Query Editor while you build in Query Builder.

Navicat provides a wide range advanced features, such as compelling code editing capabilities, smart code-completion, SQL formatting, and more.

SQL Formatting

To change the SQL statement format, simply choose from the **Format** menu -

Indent

Increase/decrease indent for the selected lines of codes.

Comment

Comment/uncomment the selected lines of codes.

Convert case

Format the selected codes into upper/lower case.

Beautify SQL (Available only in Non-Essentials Edition)

Format the selected codes with the Beautify SQL settings.

Beautify SQL With (Available only in Non-Essentials Edition)

Change the SQL beautifier options.

Option / Button	Description
Single Line Braces Word/Symbol Limit	Set the length of the short brace.
Upper case keywords	Format all the SQL keywords to upper case.
Beautify	Save and apply the SQL beautifier options.

Minify SQL (Available only in Non-Essentials Edition)


Minify the format of the SQL in the Query Editor.

Code Completion (Available only in Non-Essentials Edition)

Code completion feature in Navicat pops up a list of suggestions as you type your SQL statement in the editor. It assists you with statement completion and the available properties of database objects, for example databases, tables, fields, views etc with their appropriate icons and information. You can update the code suggestions with latest database information by choosing **Edit -> Code Completion -> Update Code Completion Info**.


To invoke code completion, just simply press '.' for the available properties of database object currently in the scope.

When the suggestion list appears, press TAB to insert the first item. You can also select the needed item using UPPER ARROW or DOWN ARROW and then press TAB or ENTER.



In addition, code completion can be invoked by typing a character or pressing ESC on your keyboard for SQL keywords/database objects.

If you select a snippet name from the list, the saved code will be inserted to the editor.



Hint: Resize the suggestion list by dragging the lower right corner.





You can enable or disable the code completion feature in [Options](#).

Clipboard Stack

When you copy or cut some codes as usual in the editor, the copied content will also be added to Clipboard Stack. Clipboard Stack can store up to 10 items and use the last-in-first-out logic. To paste an item from Clipboard Stack, you can press CTRL+SHIFT+V. Press CTRL+SHIFT+V multiple times to cycle through Clipboard Stack.

Code Folding

Code folding feature enables you to collapse blocks of code such that only the first line of the block appears in Query Editor.

A block of code that can be folded is indicated by an icon  to the left of the first line of the block. A vertical line extends from the icon to the bottom of the foldable code. In contrast, a folded block of code is indicated by an icon  to left of the code block. You can fold the block by clicking  or expand it by clicking .

```

1  SELECT
2    `film`.`film_id` AS `FID`,
3    `film`.`title` AS `title`,
4    `film`.`description` AS `description`,
5    group_concat( ...)
6  FROM
7    (((
8      (((
9        `category`
10       LEFT JOIN `film_category` ON (( ...)
11       LEFT JOIN `film` ON (( ...)
12       JOIN `film_actor` ON ((
13         `film`.`film_id` = `film_actor`.`film_id`
14       )))
15       JOIN `actor` ON ((
16         `film_actor`.`actor_id` = `actor`.`actor_id`
17       )))
18     )))
19   GROUP BY
20     `film`.`film_id`,
21     `category`.`name`

```

Brace Highlight

Navicat supports to highlight the matching brace in the editor, i.e. () .

Note: The cursor must be on a brace to show the highlight.

```

7 FROM
8 (((
9     `category`
10    LEFT JOIN `film_category` ON (( [..
13    LEFT JOIN `film` ON (( [..
16    JOIN `film_actor` ON ((
17        `film`.`film_id` = `film_actor`.`film_id`
18    )))
19    JOIN `actor` ON ((
20        `film_actor`.`actor_id` = `actor`.`actor_id`
21    )))
22 GROUP BY

```

Find and Replace

Find

The Find bar is provided for quick searching for the text in the editor. Just simply choose **Edit -> Find** from the menu or press CTRL+F, and then enter a search string.

```

1 SELECT
2     `cu`.`customer_id` AS `ID`,
3     concat( `cu`.`first_name`, _utf8mb3 ' ', `cu`.`last_name` ) AS `NAME`,
4     `a`.`address` AS `address`,
5     `a`.`postal_code` AS `zip code`,
6     `a`.`phone` AS `phone`,
7     `city`.`city` AS `city`,
8     `country`.`country` AS `country`,
9 IF
10 ( `cu`.`active`, _utf8mb3 'active', _utf8mb3 '' ) AS `notes`,
11 `cu`.`store_id` AS `SID`
12 FROM
13 (((
14     `customer` `cu`
15     JOIN `address` `a` ON ((
16         `cu`.`address_id` = `a`.`address_id`
17     )))
18     JOIN `city` ON ((
19         `a`.`city_id` = `city`.`city_id`
20     )))
21     JOIN `country` ON ((
22         `city`.`country_id` = `country`.`country_id`
23     )))

```

Find: _id Next Highlight All ☐ Replace

The search starts at the cursor's current position to the end of the file.

To find the next occurrence, just simply click **Next** or press F3.

Replace

To open the Replace bar, simply check the **Replace** box. Then, enter the text you want to search and replace.

Click the **Replace** button to replace the first occurrence.

Click the **Replace All** button to replace all occurrences automatically.

Find: _id Next Highlight All ☒ Replace

_num Replace Replace All

There are some additional options for Find and Replace, click :

Option	Description
Highlight All	Highlight all matches in the editor.
Incremental Search	Find matched text for the search string as each character is typed.

Match Case	Enable case sensitive search.
Regular Expression	Search regular expressions.
Whole Word	Return the objects that match the entire word of the search string.

Copy with Quotes

To copy the SQL statement with quotes, just simply right-click the highlighted SQL. Then, select **Copy with quotes** and choose the format.

Word Wrap

In the Word Wrap mode, the horizontal scrollbar is removed. SQL statement that exceeds the width of the editor window size wraps to the next line. To enable Word Wrap, choose **View -> Word Wrap**.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the SQL in the editor. The zooming options are available in **View -> Display -> Zoom**. The same effect can be achieved with keyboard shortcuts.

Zoom In: [CTRL+=]

Zoom Out: [CTRL+-]

Reset: [CTRL+0]

Note: Editors that are opened in different tabs or windows will not be affected by the zoom.


Query Builder (Available only in Non-Essentials Edition)

Navicat provides a useful tool called **Query Builder** for building queries, views and materialized views visually. It allows you to create and edit queries without knowledge of SQL. Even if you are familiar with SQL, the convenient and fluent graphical interface makes it easier to create relations and visualize the query.

In Query Designer, click the  **Query Builder** button to open the visual Query Builder.

All database objects are displayed on the left **Object** pane. Whereas on the middle pane, it is divided into two portions: the upper **Diagram** pane, and the lower **Criteria** pane. When building the query, you can view the auto-generated query on the right **SQL** pane.

Note: Query Builder supports SELECT statement only. Use Query Editor for creating other complex queries (e.g. INSERT, UPDATE, DELETE).



Add Objects to Query

The first step is to decide which tables and views you need to add to the query.


To add tables and views to the query, use one of the following methods:

- Drag them from the Object pane to the Diagram pane.
- Double-click them on the Object pane.

You can set aliases for tables, views and subqueries by double-clicking the object title on the Diagram pane and entering the name to use as an alias for the object name.

After you have added objects to the diagram, you can use the **FROM** tab to adjust the query to your needs.

- To change the object, click the object and select an identifier.
- To add the table alias, click **<Alias>**.




You can right-click an object on the Diagram pane and select **Remove**, or simply press DELETE key to remove the selected object from the query.

When you remove an object, Query Builder automatically removes joins that involve that object.

Choose Output Fields

To include fields in the query, use one of the following methods:

- Check the left checkbox of a field name you want to add to the query on the Diagram pane.
- To include all the fields for an object, check the * checkbox on the Diagram pane.
- To add all fields for all objects, click  on the **SELECT** tab and select **All fields(*)**.

The selected fields display on the **SELECT** tab. You can specify additional output field options.


- Check the **DISTINCT** checkbox to force the query to return distinct results.
- To add the field alias, click **<Alias>** and enter the name.
- Click the identifier and select the **Aggregate** function.
- Use the up arrow and down arrow buttons to change the order of fields.

Set Field Association

Query Builder will automatically join the tables as per the foreign key relations. If you want to associate database objects manually, just select a field from an object and drag it to a field in another object. A connector line appears between the two objects to visually represent the relationship and the join type.


There are two views to show the connector lines: Table Relation and Field Relation. The **Field Relation** view allows you to identify matching fields in two tables, while the **Table Relation** view displays the join relationship between the two tables.

All joins are initially created as INNER JOIN by default. To change the association, click or double-click the connector line on the Diagram pane or click the JOIN keyword on the **FROM** tab, and then select a join type. If a join type is not listed, you can enter a customized one in the **Custom** textbox.



To remove a join, right-click the connector line and select **Remove**.

To modify the join condition, right-click a connector line and select **Edit Join**, or click the condition on the **FROM** tab.




The pop-up menu options of the FROM tab:

Option	Description
Insert	Add an identifier, an expression or a subquery.
Insert Bracket	Add a pair of parentheses.
Remove	Remove the identifier, expression or subquery.
Clear and Convert to USING Clause	Remove the ON condition and convert it to USING clause.
Clear and Convert to ON Clause	Remove the USING condition and convert it to ON clause.
Group with Bracket	Add parentheses to group the selected conditions.
Ungroup	Remove the parentheses.

Set Filter Criteria

When retrieving data, you may want to set up a filtering expression. To filter data returned by the query, right-click a field on the Diagram pane and select **Add Field To -> WHERE** and an operator.

The condition is added to the **WHERE** tab. You can edit the value there by clicking **<Value>**. If you want to add a condition with parentheses, click **Ω+**. You can change a logical operator (and/or) by clicking it. Use the up arrow and down arrow buttons to change the order of conditions.



The pop-up menu options of the WHERE tab:

Option	Description
Toggle Negator	Reverse the meaning of the condition.
Insert	Add a condition.
Insert Custom	Add a custom condition.
Insert Bracket	Add a pair of parentheses.
Remove	Remove the condition.
Group with Bracket	Add parentheses to group the selected conditions.
Ungroup	Remove the parentheses.

Group Resulting Data

You can set the conditions for grouping query records by right-clicking a field in the Diagram pane and selecting **Add Field To -> GROUP BY**.

The condition is added to the **GROUP BY** tab. Use the up arrow and down arrow buttons to change the order of fields.

On the **HAVING** tab, you can filter summarized data or grouped data. Select the identifiers, operators, aggregate or enter expressions to include in the condition. Use the up arrow and down arrow buttons to change the order of conditions.

The pop-up menu options of the HAVING tab:

Option	Description
Toggle Negator	Reverse the meaning of the condition.
Insert	Add a condition.
Insert Custom	Add a custom condition.
Insert Bracket	Add a pair of parentheses.
Remove	Remove the condition.
Group with Bracket	Add parentheses to group the selected conditions.
Ungroup	Remove the parentheses.

Sort Resulting Data

You can set the way of sorting query records by right-clicking a field on the Diagram pane and selecting **Add Field To** -> **ORDER BY** -> **ASC** or **DESC**. The condition will be added to the ORDER BY tab.

Limit Resulting Data

On the **LIMIT** tab, you can limit your query results to those that fall within a specified range.

Offset


Specify the number of records to be skipped. It is optional.

Limit


Specify the number of records to be displayed.


Note: Available only for MySQL, PostgreSQL, SQLite and MariaDB.

Add Expressions/Subqueries

You can add an expression or a subquery to further limit the query results. On the **FROM** tab, click  and select the **Expression/Subquery** tab.

After entered an expression or a subquery, confirm editing by pressing the ENTER key. It will be added to the Diagram pane indicates that the statement contains an expression or a subquery and identifies the columns it is on.



By clicking the  button, you will be switched to a subquery layer where you can build it visually in the same way as the main query.

You can always go back to the main query by clicking **(Main Query)**.

View Generated SQL

The **SQL** pane presents a read-only, formatted representation of the SQL generated by Query Builder. You can copy the SQL that appears in the SQL pane for use in other tools. In a subquery layer, you can enable **Show Current Layer Only** to show the subquery SQL.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the diagram. Right-click anywhere on the Diagram pane and select **Zoom -> Zoom In/Zoom Out/100%**. The same effect can be achieved with keyboard shortcuts.

Zoom In: [CTRL+=]

Zoom Out: [CTRL+-]

Reset: [CTRL+0]

Query Parameters

Query supports using of parameters inside the query text. You can set query parameters to add variable values to a query each time you run it. The parameter should appear as an identifier with **\$** at its beginning, quote with [], e.g. [\$any_name].


Execute the query and the **Input Parameter** dialog is provided for you to enter the desired data you wish to search. Check the **Raw Mode** option to pass the inputted values to the query without quotation marks.

Debug Oracle Query (Available only in Non-Essentials Edition)

To debug an Oracle query, click  **Debug** on the toolbar to launch the [Oracle Debugger](#).

Enter the parameters if the query has input parameters.



Query Results

You can run the query in any servers. Select the target connection, database and/or schema from the drop-down list on the toolbar, and then click  **Run**. If the query statement is correct, the query executes and, if the query statement is supposed to return data, the **Result** tab opens with the data returned by the query. If an error occurs while executing the query, execution stops, the appropriate error message is displayed.

The **Result** tab displays the result data, returned by the query, as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Note: Navicat supports to return 20 result sets.

You can choose to show results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

You are allowed to run selected portion of query, just simply highlight SQL in Query Editor and click  **Run Selected**. To run the current statement your cursor is on (position the cursor within the desired statement), just simply click the down arrow next to the  **Run** button and select **Run Current Statement**.

Custom Tab Name

To customize the names of the result tabs, simply add `-- NAME:tab_name` or `/*NAME:tab_name*/` before each SELECT statement in the Query Editor.


```

1  -- NAME: Country
2  SELECT
3      countries.COUNTRY_ID,
4      countries.COUNTRY_NAME
5  FROM
6      countries;
7  -- NAME: Department
8  SELECT
9      departments.DEPARTMENT_ID,
10     departments.DEPARTMENT_NAME,
11     departments.LOCATION_ID,
12     departments.MANAGER_ID
13 FROM
14     departments;

```

Message	Summary	Country	Department
DEPARTMENT_ID	DEPARTMENT_NAME	LOCATION_ID	MANAGER_ID
10	Administration	1700	200
20	Marketing	1800	201
30	Purchasing	1700	114
40	Human Resources	2400	203
50	Shipping	1500	121
60	IT	1400	103
70	Public Relations	2700	204
80	Sales	2500	145
90	Executive	1700	100
100	Finance	1700	108

Show Profile and Status (Available only for MySQL and MariaDB)

To show the profile and status when running the query, simply choose **View -> Show Profile and Status** and click  **Run** on the toolbar.

The **Profile** tab displays the query profile: Table lock, System lock, Statistic, etc.

Note: For MySQL 5.0, supported from 5.0.37. For MySQL 5.1, supported from 5.1.24.

The **Status** tab displays the query status: Bytes received, Bytes sent, etc.

MongoDB

Query Editor

Query Editor allows you to create and edit a script, prepare and execute selected script. Drag-and-drop or double-click an identifier in the right **Identifiers** pane to add it to the editor.

Hint: Script will be automatically generated in Query Editor while you build in Find Builder or Aggregate Builder.

Navicat provides a wide range advanced features, such as compelling code editing capabilities, smart code-completion, script formatting, and more.

Script Formatting

To change the script format, simply choose from the **Format** menu -

Indent

Increase/decrease indent for the selected lines of codes.

Comment

Comment/uncomment the selected lines of codes.


Beautify Script (Available only in Non-Essentials Edition)

Format the selected codes.

Code Completion (Available only in Non-Essentials Edition)

Code completion feature in Navicat pops up a list of suggestions as you type your script in the editor. It assists you with database names, collection names, view names, document field names and shell methods with their appropriate icons and information. You can update the code suggestions with latest database information by choosing **Edit -> Code Completion -> Update Code Completion Info**.

Code completion can be invoked by typing a dot (.), a character or pressing ESC.



When the suggestion list appears, press TAB to insert the first item. You can also select the needed item using UPPER ARROW or DOWN ARROW and then press TAB or ENTER.

If you select a snippet name from the list, the saved code will be inserted to the editor.







Hint: Resize the suggestion list by dragging the lower right corner.

You can enable or disable the code completion feature in [Options](#).

Code Folding

Code folding feature enables you to collapse blocks of code such that only the first line of the block appears in Query Editor.

A block of code that can be folded is indicated by an icon  to the left of the first line of the block. A vertical line extends from the icon to the bottom of the foldable code. In contrast, a folded block of code is indicated by an icon  to left of the code block. You can fold the block by clicking  or expand it by clicking .

```
1 db.getCollection("employees").find({
2   $and: [{
3     "EMPLOYEE_ID": 102
4   }, {
5     $or: [{
6       ...
7     }]
8   }]
9 })
```

Brace Highlight

Navicat supports to highlight the matching brace in the editor, i.e. ().

Note: The cursor must be on a brace to show the highlight.

```
1 db.getCollection("employees").find({
2   $and: [{
3     "EMPLOYEE_ID": 102
4   }, {
5     $or: [{
6       "JOB_ID": "TA-1"
7     }, {
8       "MANAGER_ID": 103
9     }]
10  }]
11 })
```

Find and Replace

Find

The Find bar is provided for quick searching for the text in the editor. Just simply choose **Edit -> Find** from the menu or press CTRL+F, and then enter a search string.



The search starts at the cursor's current position to the end of the file.


To find the next occurrence, just simply click **Next** or press F3.


Replace

To open the Replace bar, simply check the **Replace** box. Then, enter the text you want to search and replace.

Click the **Replace** button to replace the first occurrence.

Click the **Replace All** button to replace all occurrences automatically.



There are some additional options for Find and Replace, click :

Option	Description
Highlight All	Highlight all matches in the editor.
Incremental Search	Find matched text for the search string as each character is typed.
Match Case	Enable case sensitive search.
Regular Expression	Search regular expressions.
Whole Word	Return the objects that match the entire word of the search string.

Copy with Quotes

To copy the script with quotes, just simply right-click the highlighted script. Then, select **Copy with quotes** and choose the format.

Word Wrap

In the Word Wrap mode, the horizontal scrollbar is removed. Script that exceeds the width of the editor window size wraps to the next line. To enable Word Wrap, choose **View -> Word Wrap**.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the script in the editor. The zooming options are available in **View -> Display -> Zoom**. The same effect can be achieved with keyboard shortcuts.

Zoom In: [CTRL+=]

Zoom Out: [CTRL+-]


Reset: [CTRL+0]

Note: Editors that are opened in different tabs or windows will not be affected by the zoom.

Find Builder (Available only in Non-Essentials Edition)

Navicat provides Find Builder for building queries visually to select documents in a collection or view. It allows you to create and edit queries without knowledge of the *find* command.

In Query Designer, click the  **Find Builder** button to open the visual Find Builder.



Select the name of the collection or view to query from the **Collection/View** drop-down list.

Filter

In this tab, you can specify selection filters for the query. Documents that meet the conditions will be returned. If you not specify the filter, all documents will be returned. See [Filter Wizard](#) for details.

Projection

In this tab, you can choose which fields to include or exclude in the returned documents. If you not specify the projection, all fields will be returned.

Sort

In this tab, you can sort the returned documents by fields in ascending or descending order.


Limit

In this tab, you can limit the maximum number of documents to return and set the number of documents to skip.

Aggregate Builder (Available only in Non-Essentials Edition)

Navicat provides Aggregate Builder for building queries visually to return computed results. It allows you to create and edit queries without knowledge of the *aggregate* command.

In Query Designer, click the  **Aggregate Builder** button to open the visual Aggregate Builder.




Select the name of the collection or view to query from the **Collection/View** drop-down list.

Pipeline

In this tab, you can add aggregation pipeline stages. In the **Operator** column, select an expression operator. An expression template will be generated in the **Expression** column, you can modify the template.

Query Results

You can run the query in any servers. Select the target connection and database from the drop-down list on the toolbar, and then click  **Run**. If the query script is correct, the query executes and, if the query script is supposed to return data, the **Result** tab opens with the data returned by the query. If an error occurs while executing the query, execution stops, the appropriate error message is displayed.

The **Result** tab displays the result data, returned by the query, as a grid. Data can be displayed in three modes: Grid View, Tree View and JSON View. See [Data Viewer](#) for details.

Note: Navicat only returns the last result data.

You can choose to show results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

You are allowed to run selected portion of query, just simply highlight script in the editor and click  **Run Selected**.

Redis

Query Editor

Query Editor allows you to create and edit commands, prepare and execute selected queries. You can define multiple commands in one query window.

Navicat provides a wide range advanced features, such as compelling code editing capabilities, smart code-completion, command formatting, and more.

Command Formatting

To change the command format, simply choose from the **Format** menu -

Indent

Increase/decrease indent for the selected lines of codes.

Comment

Comment/uncomment the selected lines of codes.


Convert case

Format the selected codes into upper/lower case.

Code Completion (Available only in Non-Essentials Edition)


Code completion feature in Navicat pops up a list of suggestions as you type your command in the editor. It assists you with command completion and the available functions with their appropriate icons and information.

Code completion can be invoked by typing a character or pressing ESC.



When the suggestion list appears, press TAB to insert the first item. You can also select the needed item using UPPER ARROW or DOWN ARROW and then press TAB or ENTER.

If you select a snippet name from the list, the saved code will be inserted to the editor.



Hint: Resize the suggestion list by dragging the lower right corner.

You can enable or disable the code completion feature in [Options](#).

Clipboard Stack

When you copy or cut some codes as usual in the editor, the copied content will also be added to Clipboard Stack. Clipboard Stack can store up to 10 items and use the last-in-first-out logic. To paste an item from Clipboard Stack, you can press CTRL+SHIFT+V. Press CTRL+SHIFT+V multiple times to cycle through Clipboard Stack.

Brace Highlight

Navicat supports to highlight the matching brace in the editor, i.e. () .


Note: The cursor must be on a brace to show the highlight.

```
1 ACL SETUSER john on >Jho!jkk >Tahc*mcx nocommands allkeys allchannels
2 ACL SETUSER temp on >Xtxsfaf3 nocommands allkeys allchannels
3 ACL SETUSER usr1 on clearselectors [(nocommands +@read)] (nocommands ~k1 ~k2 ~k3)
4 ACL SETUSER amy on ~* &* +@all >amy123
```

Find and Replace

Find

The Find bar is provided for quick searching for the text in the editor. Just simply choose **Edit -> Find** from the menu or press CTRL+F, and then enter a search string.



The search starts at the cursor's current position to the end of the file.


To find the next occurrence, just simply click **Next** or press F3.

Replace

To open the Replace bar, simply check the **Replace** box. Then, enter the text you want to search and replace.

Click the **Replace** button to replace the first occurrence.

Click the **Replace All** button to replace all occurrences automatically.



There are some additional options for Find and Replace, click :

Option	Description
Highlight All	Highlight all matches in the editor.
Incremental Search	Find matched text for the search string as each character is typed.
Match Case	Enable case sensitive search.
Regular Expression	Search regular expressions.
Whole Word	Return the objects that match the entire word of the search string.

Copy with Quotes

To copy the command with quotes, just simply right-click the highlighted command. Then, select **Copy with quotes** and choose the format.

Word Wrap

In the Word Wrap mode, the horizontal scrollbar is removed. Command that exceeds the width of the editor window size wraps to the next line. To enable Word Wrap, choose **View -> Word Wrap**.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the command in the editor. The zooming options are available in **View -> Display -> Zoom**. The same effect can be achieved with keyboard shortcuts.


Zoom In: [CTRL+=]

Zoom Out: [CTRL+-]

Reset: [CTRL+0]

Note: Editors that are opened in different tabs or windows will not be affected by the zoom.



Query Results

You can run the query in any servers. Select the target connection and database from the drop-down list on the toolbar, and then click  **Run**. If the query command is correct, the query executes and, if the query command is supposed to return data, the **Result** tab opens with the data returned by the query. If an error occurs while executing the query, execution stops, the appropriate error message is displayed.

Navicat displays query results in a user-friendly format. The **Result** tab displays the result data, returned by the query, as a grid. See [Data Viewer](#) for details.


Note: Navicat supports to return 20 result sets.

You can choose to show results below the editor or in a new tab by choosing **View -> Result -> Show Below Editor** or **Show in New Page**.

You are allowed to run selected portion of query, just simply highlight commands in the editor and click  **Run Selected**. To run the current command your cursor is on (position the cursor within the desired command), just simply click the down arrow next to the  **Run** button and select **Run Current Statement**.

Custom Tab Name


To customize the names of the result tabs, simply add `// NAME:tab_name` before each command in the Query Editor.




```
1 // NAME:database
2 CONFIG GET databases
3
4 // NAME:rule
5 ACL GETUSER readonly
6
7 // NAME:data
8 SCAN 1050 COUNT 100
```

Message	Summary	database	rule	data
#	Value			
▶ 1	flags			
2-1	on			
2-2	nopass			
3	passwords			
4-1	(Null)			
5	commands			
6	+@all -@write			
7	keys			
8	~*			
9	channels			

Code Snippets (Available only in Non-Essentials Edition)

Code Snippets provide an easy way for you to insert reusable code into editor when writing statements or scripts. The Code Snippet pane is on the right side of the editor. If the editor window is docked to the Navicat main window, you can click the  icon in the Information pane to open the library.

The library includes built-in and user-defined snippets. Choose a label from the drop-down list or enter a search string in the Search box to filter the list. If you want to show the available snippets according to your database type, you can right-click anywhere on the library and disable **Show Snippets For Other Database Type**.




Built-in snippets are non-editable. A user-defined snippet can be edited by double-clicking it in the library. If you want to hide the built-in snippets, you can right-click anywhere on the library and disable **Show Preset Snippets**.

Use Code Snippets

There are two ways to insert a snippet into the editor.

- You can start typing the name of a snippet in the editor. Smart code completion will pop up a list of suggestions for the word completion automatically. Select a snippet name from the list, the saved code will be inserted to the editor.



- You can simply drag and drop a snippet from the library into the editor.

After inserting the snippet with placeholders to the editor, you can easily navigate to them by clicking on one of the placeholders, and then using the TAB key and entering the information.


```

1  SELECT
2    [field_name1],
3    [field_name2],
4    [field_name3]
5  FROM
6    [table1]
7  INNER JOIN
8    [table2] ON [condition1]



```

Create Code Snippets

You can create your own code snippets and add them to the library. To create a code snippet, select your desired code in the editor, then right-click and select **Create Snippet**.

Alternatively, click  in the Code Snippet pane. If you use this method, you must manually enter the code in the New Snippet window; code selected in the editor is not automatically added to the Code box.

Hint: Code snippets (.nsnippet) are stored in the **snippets** folder under the [Profiles Location](#).

Option / Button	Description
Untitled text box	Enter the name of the snippet that displays in the library and the code completion list.
Database Type	Choose the database server type of the snippet.
Label	Choose an existing label or enter a new label name for the snippet.
Remarks	Enter a description for the snippet that displays in the library.
Code	Enter the code.
	Add a placeholder by highlighting any words in the code and click this button. The placeholder will be highlighted in light green.
	Remove a placeholder by highlighting it in the code and click this button.

Move / Copy Snippet To Project


If you have logged in to Navicat Cloud or On-Prem Server, you can synchronize the custom snippet in My Connections to a project.

- Right-click a snippet and select **Move Snippet To** or **Copy Snippet To**.
- Select an existing project.
- The snippet will be moved or copied to the project.

Hint: You can move / copy a snippet in a project to My Connections in a similar way.

Chapter 8 - Model (Available only in Navicat Premium and Enterprise Edition)

About Model

Model is a powerful tool for creating and manipulating database models. In the main window, click  **Model** to open the model object list.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB.

Some of key features are listed here:

- Create and manipulate conceptual/logical/physical models.

Note: Only Navicat Premium supports conceptual and logical models.

- Reverse engineer a database/schema, tables or views to a physical model.
- Forward engineer a physical model to a sql file or database/schema.
- Create and edit table structures directly.

Hint: Model files (.ndm2/.ndml2/.ndmc2) are saved under the [Profiles Location](#). To open the folder, right-click a model file and select **Open Containing Folder**. If the model is synchronized to [Navicat Cloud](#) or [On-Prem Server](#), it will be stored in the cloud.

Open an external model file

1. In the menu bar, choose **File -> Open External File -> Model**.
2. Browse the file and click **Open** in the dialog window.

Save an opened external file as a Navicat model


1. In Model Designer, choose **File -> Save to Navicat**.
2. Enter the model name and choose the save location.
3. Click **OK**.

Save a Navicat model as an external file

1. In Model Designer, choose **File -> Save As External File**.
2. Choose the save path and enter the file name.
3. Click **Save**.

Model Window

The Model Window consists of a toolbar, several panes and a diagram canvas for you to design your model. A model file can have more than one diagram. Each diagram is represented by a tab in the model. To create a new diagram, choose **Diagram -> New Diagram** from the menu bar.



1 Toolbar

The Toolbar is located near the top of the Model Window. The buttons display in the toolbar depend on the model type (physical, logical and conceptual). You can use the toolbar to perform some basic tasks, such as adding tables, entities or views, applying Auto Layout feature, etc.

2 Explorer Pane

The Explorer pane has two tabs: **Model** and **Diagram**. The Model tab holds all schemas, tables, views or entities in the model, including those used in each individual diagram. You can simply drag an object from the Model tab and drop to the active diagram canvas. The Diagram tab holds all the objects (tables, views, foreign keys, layers, notes, images, etc) added to the active diagram. If the Explorer pane is hidden, choose **View -> Show Explorer** from the menu bar.

3 History Pane

The History pane shows all the actions that you have taken. Simply click an action to restore that state. If the History pane is hidden, choose **View -> Show Explorer** and **Show History** from the menu bar.

4 Properties Pane

The Properties pane includes the **Model**, **Diagram** and **Object** tabs for setting default properties for your model. You can edit the properties settings of the model, the active diagram and the selected objects quickly. If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Option	Description
Begin Arrow Style	The style of the arrow's back.
Black and White	Check this box to change the diagram color to black and white.
Bold	Check this box or press CTRL+B to bold the table, view, entity, foreign key, relation or shape.
Border Color	The color of the shape's border.
Cap Style	The cap style of the line/arrow.
Case Sensitivity	The case sensitivity of the table or view names. Available only for MySQL and MariaDB models.
Color	The color of the object.
Dash Style	The dash style of the line/arrow.
Database Name	The database name of the table/view.
Database Type	The database type of the model.
Database Version	The database version of the model.
Default Database	The default database of the model.
Default Schema	The default schema of the model.
Diagram Notation	The notation of the diagram. The notation options are depended on the model type.
End Arrow Style	The style of the arrow's front.
Entity Font Name	The font name of the entities.
Entity Font Size	The font size of the entities.
Font Bold	Check this box to bold the note/label font.
Font Color	The font color of the note, label or layer.
Font Italic	Check this box to apply an italic style to the note or label font.
Font Name	The font name of the note, label or layer.
Font Size	The font size of the note, label or layer.
Height	The height of the object.
Height (pages)	The height of the diagram (number of papers).
Join Style	The join style of the line/arrow.
Left	The number of pixels from the object to the left side of the canvas.
Model Type	The type of the model.
Model Version	The version of the model.
Name	The name of the object.
Opacity	The transparency of the image/shape. The value for this can be between 0 and 100. Use 100 for opacity and 0 for transparent.
Referenced Cardinality	The foreign key/relation cardinality of the referenced (parent) table or entity.
Referencing Cardinality	The foreign key/relation cardinality of the referencing (child) table or entity.
Schema Name	The schema name of the table/view.
Show Database Names	Check this box to show the database names of the tables/views in

	the diagram.
Show Entity Comments	Check this box to show the entity comments in the diagram.
Show Field Comments	Check this box to show the field comments in the diagram.
Show name	Check this box to show the name of the foreign key, relation or shape.
Show Schema Names	Check this box to show the schema names of the tables/views in the diagram.
Show Table Comments	Check this box to show the table comments in the diagram.
Show View Relationships	Check this box to show the relationship line of the view.
Table Font Name	The font name of the tables.
Table Font Size	The font size of the tables.
Top	The number of pixels from the object to the top of the canvas.
Visible	Check this box to show the foreign key/relation lines.
Width	The width of the object.
Width (pages)	The width of the diagram (number of papers).

⑤ Overview Pane

The Overview pane displays the whole active diagram in the canvas. To zoom in or zoom out the selected area of the diagram, adjust the slider. Same effect can be achieved with keyboard shortcuts:

Zoom In: [CTRL++] or [CTRL+Mousewheel Up]

Zoom out: [CTRL+-] or [CTRL+Mousewheel Down]

Reset Zoom: [CTRL+0]

If the Overview pane is hidden, choose **View -> Show Properties** and **Show Overview** from the menu bar.

⑥ Diagram Canvas

You can design your diagram on the Diagram Canvas. All added objects can be moved (by dragging them with mouse or by keyboard), resized, aligned to the grid, etc.

Physical Models

Create Physical Models

Navicat allows you to create physical models, including tables, fields, views, foreign key constraints and other physical properties of the database/schema.

In the **New Model** window, choose the **Model Type** and select the target **Database** and **Version** if necessary.

After creating a physical model, you can [compare and synchronize](#) it to an existing database/schema or [export](#) it to a SQL file.

Add Databases / Schemas


When creating a new model, a database/schema (named Default) is automatically created and it is the default database/schema. All newly added objects (tables and views) are belonged to the default database/schema.



You can view all databases/schemas with their objects as tree structure on the Explorer's Model tab.

The pop-up menu options of a database/schema in the Explorer's Model tab include:

Option	Description
New Database / New Schema	Create a database/schema.
Delete Database / Delete Schema	Delete the selected database/schema including its objects from the model. The default database/schema cannot be deleted.
Rename	Change the name of the database/schema.
Set as Default Database / Set as Default Schema	Set the selected database/schema as the default database/schema.

Add Tables

To add a new table, click the  button from the toolbar and click anywhere on the canvas. To add an existing table from the Explorer's Model tab, simply drag and drop the selected table from the Model tab to the canvas.

For Default diagram notation, the  icon means the field is a primary key. The  icon indicates that the field serves as an index.


Note: If you right-click a field, you can choose to add, insert, delete, rename the field and set the field as primary key.

The pop-up menu options of the table object in the canvas include:

Option	Description
Design Table	Edit the table structure in a table designer, e.g. fields, indexes, foreign keys, etc. The tabs and options in the designer depend on the diagram database type you are chosen.
Add Related Objects	Add all related tables/views to the selected table.
Add Field	Add fields to the existing table.
Cut	Remove the table from the diagram and put it on the clipboard.
Copy	Copy the table from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Tables	Select all tables in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete a table from the diagram or from both diagram and model.
Rename	Change the name of the table.
Color	Change the color of the table.

Size to Fit	Resize the table automatically to fit its contents.
Bring to Front	Bring the table to the foreground.
Send to Back	Move the table to the background.

Add Views


To add a new view, click the  button from the toolbar and click anywhere on the canvas. To add an existing view from the Explorer's Model tab, simply drag and drop the selected view from the Model tab to the canvas.

Note: If you right-click the view connector, you can choose to add or delete vertices and change its color, or go to the source view or the target table.

The pop-up menu options of the view object in the canvas include:

Option	Description
Design View	Edit the view structure in a view designer. The tabs and options in the designer depend on the diagram database type you are chosen.
Add Related Objects	Add all related tables/views to the selected view.
Cut	Remove the view from the diagram and put it on the clipboard.
Copy	Copy the view from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Views	Select all views in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete a view from the diagram or from both diagram and model.
Rename	Change the name of the view.
Color	Change the color of the view.
Size to Fit	Resize the view automatically to fit its contents.
Bring to Front	Bring the view to the foreground.
Send to Back	Move the view to the background.

Add Foreign Keys

To add a foreign key, click the  button from the toolbar and drag and drop a field from the child table to the parent table. To show/hide the linked name label, simply check/uncheck the **Show Name** option in the Properties pane.

When you move your mouse over a foreign key connector, the border of the parent and the child tables turn to green and blue respectively. Also, the referenced fields and the referencing fields are highlighted.

The pop-up menu options of the foreign key in the canvas include:

Option	Description
Design Relation	Edit the foreign key in a table designer. The options in the designer depend on the diagram database type you are chosen.

Cardinality on table_name1	Set the cardinality on table_name1: None, One and Only One, Many, One or Many, Zero or One, Zero or Many.
Cardinality on table_name2	Set the cardinality on table_name2: None, One and Only One, Many, One or Many, Zero or One, Zero or Many.
Add Vertex	Add a vertex on a foreign key connector.
Delete Vertex	Delete a vertex on a foreign key connector.
Delete All Vertices	Delete all vertices on a foreign key connector.
Go to Source	Go to and select the source (child) table.
Go to Target	Go to and select the target (parent) table.
Paste	Paste the content from the clipboard into the diagram.
Select All Relations	Select all foreign keys in the diagram.
Delete from Diagram and Model	Delete a foreign key from both diagram and model.
Color	Change the color of the foreign key.


Logical Models



Create Logical Models

Navicat Premium allows you to create logical models, including entities, attributes and relations.

In the **New Model** window, choose **Logical** as **Model Type**.

Add Entities

To add a new entity, click the  button from the toolbar and click anywhere on the canvas. To add an existing entity from the Explorer's Model tab, simply drag and drop the selected entity from the Model tab to the canvas.

For Default diagram notation, the  icon means the attribute is a primary key. The  icon indicates that the attribute serves as an index.


Note: If you right-click an attribute, you can choose to add, insert, delete, rename the attribute and set the attribute as primary key.

The pop-up menu options of an entity object in the canvas include:

Option	Description
Design Entity	Edit the entity structure in an Entity Designer, e.g. attributes and relations.
Add Related Objects	Add all related entities to the selected entity.
Add Attribute	Add attributes to the existing entity.
Cut	Remove the entity from the diagram and put it on the clipboard.
Copy	Copy the entity from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.

Select All Entities	Select all entities in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete an entity from the diagram or from both diagram and model.
Rename	Change the name of the entity.
Color	Change the color of the entity.
Size to Fit	Resize the entity automatically to fit its contents.
Bring to Front	Bring the entity to the foreground.
Send to Back	Move the entity to the background.

Add Relations

To add a relation, click the  button from the toolbar and drag and drop an attribute from the child entity to the parent entity. To show/hide the linked name label, simply check/uncheck the **Show name** option in the Properties pane.

When you move your mouse over a relation connector, the border of the parent and the child entities turn to green and blue respectively. Also, the referenced attributes and the referencing attributes are highlighted.

The pop-up menu options of the relation in the canvas include:

Option	Description
Design Relation	Edit the relation in an Entity Designer.
Cardinality on entity_name1	Set the cardinality on entity_name1: None, One and Only One, Many, One or Many, Zero or One, Zero or Many.
Cardinality on entity_name2	Set the cardinality on entity_name2: None, One and Only One, Many, One or Many, Zero or One, Zero or Many.
Add Vertex	Add a vertex on a relation connector.
Delete Vertex	Delete a vertex on a relation connector.
Delete All Vertices	Delete all vertices on a relation connector.
Go to Source	Go to and select the source (child) entity.
Go to Target	Go to and select the target (parent) entity.
Paste	Paste the content from the clipboard into the diagram.
Select All Relations	Select all relations in the diagram.
Delete from Diagram and Model	Delete a relation from both diagram and model.
Color	Change the color of the relation.


Conceptual Models

Create Conceptual Models

Navicat Premium allows you to create conceptual models, including entities and relations.

In the **New Model** window, choose **Conceptual** as **Model Type**.


Add Entities

To add a new entity, click the  button from the toolbar and click anywhere on the canvas. To add an existing entity from the Explorer's Model tab, simply drag and drop the selected entity from the Model tab to the canvas.

The pop-up menu options of the entity object in the canvas include:

Option	Description
Add Related Objects	Add all related entities to the selected entity.
Cut	Remove the entity from the diagram and put it on the clipboard.
Copy	Copy the entity from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Entities	Select all entities in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete an entity from the diagram or from both diagram and model.
Rename	Change the name of the entity.
Color	Change the color of the entity.
Size to Fit	Resize the entity automatically to fit its contents.
Bring to Front	Bring the entity to the foreground.
Send to Back	Move the entity to the background.

Add Relations

To add a relation, click the  button from the toolbar and drag the child entity and drop to the parent entity. To show/hide the linked name label, simply check/uncheck the **Show name** option in the Properties pane.

When you move your mouse over a relation connector, the border of the parent and the child entities turn to green and blue respectively.

The pop-up menu options of the relation in the canvas include:

Option	Description
Cardinality on entity_name1	Set the cardinality on entity_name1: None, One and Only One, Many, One or Many, Zero or One, Zero or Many.
Cardinality on entity_name2	Set the cardinality on entity_name2: None, One and Only One, Many, One or Many, Zero or One, Zero or Many.
Add Vertex	Add a vertex on a relation connector.
Delete Vertex	Delete a vertex on a relation connector.
Delete All Vertices	Delete all vertices on a relation connector.
Go to Source	Go to and select the source (child) entity.
Go to Target	Go to and select the target (parent) entity.
Paste	Paste the content from the clipboard into the diagram.
Select All Relations	Select all relations in the diagram.

Delete from Diagram and Model	Delete a relation from both diagram and model.
Color	Change the color of the relation.

Diagram Layout

Work with Diagram Canvas

Show Grid

To turn the grid on in the diagram canvas, choose **View -> Show Grid** from the menu bar.

Snap to Grid

To align objects on the canvas with the grid, choose **View -> Snap To Grid** from the menu bar.

Keep Orthogonal Layout

To keep the lines consisting of horizontal and vertical segments when moving an object, choose **View -> Keep Orthogonal Layout** from the menu bar.

Change Diagram Notation

To change the notation of the diagram, choose **Diagram -> Diagram Notation** from the menu bar.

Note: The options depend on the diagram type you are chosen.

Option	Description
Default	The default notation style used in Navicat.
Simple	A simple notation style. The table or view will only show the name.
IE (Crow's Foot)	Crow's Foot notation style.
IDEF1X	The ICAM DEFinition language information modeling method.
UML	Universal Modeling Language style.
Classic	A classic notation style.
Black and White	Change the color of the diagram to black and white.
Show Database Names	Show the database names of the tables and views in the diagram.
Show Schema Names	Show the schema names of the tables and views in the diagram.
Show View Relationships	Show the relationship lines of views in the diagram.

Change Diagram Dimensions

To change the number of pages used in the diagram, choose **Diagram -> Diagram Dimensions** from the menu bar and set the **Width** and the **Height**.

Align Objects

To align objects on the canvas, select more than one object (tables, entities, views, notes, labels, images or shapes), then right-click and select **Alignment** -> **Align Left**, **Align Center**, **Align Right**, **Align Top**, **Align Middle** or **Align Bottom**.


Change Objects Distribution

To distribute objects on the canvas, select more than one object (tables, entities, views, notes, labels, images or shapes), then right-click and select **Distribute** -> **Horizontal** or **Vertical**.

Change Page Setup


To change paper size, orientation and margins, choose **File** -> **Page Setup**.

Apply Auto Layout

To automatically arrange objects on the canvas, click the  button. To change the Auto Layout format settings, simply choose **Diagram** -> **Auto Layout with** from the menu bar and set the following options:

Option	Description
Auto Diagram Dimension	Choose the suitable diagram dimension automatically.
Auto Size Tables To Fit	Resize the table to fit its content automatically.
Quality	The quality of the auto layout output.
Object Distance	The distance between the objects in the diagram.


Add Labels

Labels are typically used to help document the diagram design process. For example, to explain a grouping table objects. To add a new label, click the  button from the toolbar and click anywhere on the canvas.

The pop-up menu options of the label object in canvas include:

Option	Description
Edit	Change the content of the label.
Cut	Remove the label from the diagram and put it on the clipboard.
Copy	Copy the label from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Labels	Select all labels in the diagram.
Delete from Diagram	Delete a label from the diagram.
Size to Fit	Resize the label automatically to fit its contents.
Bring to Front	Bring the label to the foreground.
Send to Back	Move the label to the background.


Add Notes

Notes are typically used to help document the diagram design process. For example, to explain a grouping table objects. To add a new note, click the  button from the toolbar and click anywhere on the canvas.

The pop-up menu options of the note object in canvas include:

Option	Description
Edit	Change the content of the note.
Cut	Remove the note from the diagram and put it on the clipboard.
Copy	Copy the note from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Notes	Select all notes in the diagram.
Delete from Diagram	Delete a note from the diagram.
Color	Change the color of the note.
Size to Fit	Resize the note automatically to fit its contents.
Bring to Front	Bring the note to the foreground.
Send to Back	Move the note to the background.


Add Images

You can insert images (BMP, JPG, JPEG or PNG files) to your model for design or identification purposes. To add a new image, click the  button from the toolbar and click anywhere on the canvas. Then, select an image file in the Open dialog box.

The pop-up menu options of the image object in canvas include:

Option	Description
Reset Size	Reset the size of the image to its original size.
Reset Aspect Ratio	Maintain the image original width to height ratio.
Cut	Remove the image the diagram and put it on the clipboard.
Copy	Copy the image from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Images	Select all images in the diagram.
Delete from Diagram	Delete an image from the diagram.
Bring to Front	Bring the image to the foreground.
Send to Back	Move the image to the background.

Add Shapes


Navicat includes some pre-defined shapes for creating database model diagrams: line, arrow, rectangle, ellipse, user, database, cloud, trigger, server, desktop or mobile. To add a new shape, click the  button from the toolbar and choose the type of shape. Then, click anywhere on the canvas. To show/hide the linked name label, simply check/uncheck the **Show name** option in the Properties pane.

The pop-up menu options of the shape object in canvas include:

Option	Description
Reset Aspect Ratio	Maintain the shape original width to height ratio.

	Only for rectangle, ellipse, user, database, cloud, trigger, server, desktop and mobile.
Cut	Remove the shape from the diagram and put it on the clipboard.
Copy	Copy the shape from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Shapes	Select all shapes in the diagram.
Delete from Diagram	Delete a shape from the diagram.
Color	Change the color of the shape.
Border Color	Change the color of the shape's border. Only for rectangle, ellipse, user, database, cloud, trigger, server, desktop and mobile.
Begin Arrow Style	Change the style of the arrow's back. Only for arrow.
End Arrow Style	Change the style of the arrow's front. Only for arrow.
Add Vertex	Add a vertex on a line or arrow. Only for line and arrow.
Delete Vertex	Delete a vertex on a line or arrow. Only for line and arrow.
Delete All Vertices	Delete all vertices on a line or arrow. Only for line and arrow.
Bring to Front	Bring the shape to the foreground.
Send to Back	Move the shape to the background.

Add Layers

Layers are used to help organize objects (e.g. tables, notes, images, etc) on the canvas. You can add all related objects to the same layer. For example, you may choose to add all your sales related tables to one layer. To add a new layer, click the  button from the toolbar and click anywhere on the canvas.

The pop-up menu options of the layer object in canvas include:

Option	Description
Cut	Remove the layer from the diagram and put it on the clipboard.
Copy	Copy the layer from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Select All Layers	Select all layers in the diagram.
Delete from Diagram	Delete a layer from the diagram.
Color	Change the color of the layer.
Size to Fit	Resize the layer automatically to fit its contents.
Bring to Front	Bring the layer to the foreground.
Send to Back	Move the layer to the background.

Reverse Engineering

Reverse Engineering is one of the key features of Model. This feature allows you to load already existing database structures to create new diagrams. It supports importing databases, schema, tables or views.

Navicat provides a step-by-step wizard for you to complete the task:

1. Choose **File -> Import from Database**.
2. Select a connection.
3. Select databases, schemas, tables or views you want to import.
4. Click **Start**.

You can also simply create a new model using reverse engineering in the Navicat main window. Right-click an opened database/schema, tables or views and select **Reverse Database to Model**, **Reverse Schema to Model**, **Reverse Tables to Model** or **Reverse Views to Model** from the pop-up menu.

Forward Engineering

Synchronize to Database

The **Synchronize to Database** feature allows you to compare a physical model with an existing database or schema, states the differences between their structures, and offers synchronizing the structures in model to the target connection.

Navicat provides a step-by-step wizard for you to complete the task:

1. Choose **File -> Synchronize to Database**.
2. Select the source database, schema, and select the target connection, database, schema.
3. Click **Options** and select the compare / advanced options.
4. Click **Compare** to show the differences between source and target objects.
5. Select the objects you want to synchronize.
6. Click **Next** to generate a set of scripts.
7. Click **Start**.

Choose Connections

The first step is to define connections, databases and/or schemas for the source model and the target connection.

Choose Comparing Options

Then, click the **Options** button to select the compare / advanced options for the synchronization process.

Note: The following options depend on the diagram database type you are chosen and sort in ascending order.

Compare auto increment value

Check this option if you want to compare the auto increment values of tables.

Compare character set

Check this option if you want to compare the character sets of tables.

Compare checks

Check this option if you want to compare checks.

Compare collation

Check this option if you want to compare the collations of tables.

Compare definers

Check this option if you want to compare the definers of views.

Compare excludes

Check this option if you want to compare excludes.

Compare foreign keys

Check this option if you want to compare table foreign keys.

Compare identity last value

Check this option if you want to compare the identity last values of tables.

Compare indexes

Check this option if you want to compare indexes.

Compare owners

Check this option if you want to compare the owners of the objects.

Compare partitions

Check this option if you want to compare table partitions.

Compare primary keys

Check this option if you want to compare table primary keys.

Compare rules

Check this option if you want to compare rules.

Compare storage

Check this option if you want to compare table storages.

Compare table options

Check this option if you want to compare other table options.

Compare tables

Check this option if you want to compare tables.

Compare triggers

Check this option if you want to compare triggers.

Compare uniques

Check this option if you want to compare uniques.

Compare views

Check this option if you want to compare views.

Drop with CASCADE

Check this option if you want to drop the dependent database objects with the CASCADE option.

Identifier Case Sensitivity


Ignore or consider the case of identifiers when mapping, or use the server default setting.

Start Comparison

Click the **Compare** button to compare the source model and the target database.

View Comparison Results


After comparing structures, the tree view shows the differences between the source and target databases or schemas. All objects are checked in the tree view by default. Uncheck the objects you do not want to apply to the target. You can expand the table objects to view the detailed structure.



You can choose to group the objects in the tree views by object types or operations by selecting **Group by object type** or **Group by operation**.

Operation	Description
→	Object exists in both source and target databases/schemas, but they have different definition. The target object will be modified based on the source object.
+	Object does not exist in the target database/schema. It will be created in the target.
×	Object does not exist in the source database/schema. The target object will be deleted.
=	Object exists in both source and target databases/schemas and they have identical definition. No operation will be applied.

When you selected an object in the tree view, the **DDL Comparison** tab shows the DDL statements of that object in the source and the target, and the **Deployment Script** tab shows the detailed SQL statements of the object that will be executed in the target databases.




Click the **Next** button to show the scripts of all selected objects.

Edit & Execute Selected Scripts

You can view all scripts that will be executed in the target database in the **Deployment Script** tab.

Deployment Options Button	Description
Deployment Options	Continue on error - Ignore errors that are encountered during the execution process if necessary.
Edit Script	Open the Edit Deployment Script window to rearrange the order of the scripts.
Copy Script to Clipboard	Copy all scripts from the Deployment Script tab to the clipboard.
Open Script in Query Editor	Open a new query window and display the scripts.

In the **Edit Deployment Script** window, use the arrow buttons to move the scripts.



Then, click the **Start** button to execute the scripts. The window will display the execution progress, execution time, and success or failure messages.

Export SQL

After finishing your model, you can save table structures and relations from the model into a script file. The **Export SQL** feature generates a SQL file for the script. To start the Export SQL feature, choose **File -> Export SQL** from the menu bar.

General Properties

File

Set the output file name and location.

Objects

Choose objects in the model you wish to export.

Advanced Properties

Note: The following options depend on the diagram database type you are chosen and sort in ascending order.

Include auto increment

Include table auto increment in the SQL file with this option is on.

Include character set

Include table and field character set in the SQL file with this option is on.

Include checks

Include checks in the SQL file with this option is on.

Include collation

Include table collation in the SQL file with this option is on.

Include Drop SQL

Include drop object SQL statements in the SQL file with this option in on.

Include Drop With CASCADE

Include drop object SQL statements with CASCADE option in the SQL file with this option in on.

Include excludes

Include excludes in the SQL file with this option is on.

Include foreign keys

Include foreign keys in the SQL file with this option is on.

Include indexes

Include indexes in the SQL file with this option is on.

Include primary keys

Include primary keys in the SQL file with this option is on.

Include rules

Include rules in the SQL file with this option is on.

Include schema

Include the schema name in the SQL file with this option is on. Otherwise, only object names are included in SQL statements.

Include triggers

Include triggers in the SQL file with this option is on.

Include uniques

Include uniques in the SQL file with this option is on.

Server Version

Select the server version for the SQL file.

Model Conversion

Navicat allows you to convert your models from one database type to another database type, e.g. MariaDB 10.0 physical model to PostgreSQL 9.0 physical model.

During the conversion, all data types are converted automatically. The conversion process does not change the SQL syntax of views if converting from one database type to another. If the target database version is MySQL 4.0 or below, all views will be removed.

With Navicat Premium, you can also convert your models from one model type to another model type. If you convert a physical model to logical/conceptual model, all views will be converted to entities.

To convert an opened model file, choose **File -> Convert Model To**. Then, choose the **Model Type** and select the target **Database** and **Version** if necessary.

Print & Export Model

Preview a model

To preview the pages before printing, simply click the  button. The model can be printed to the printer or exported to various file formats.

Print to a printer

Choose **File -> Print** to send your diagram directly to the printer. You can set the printer option in the pop-up window.

Export to a file

Choose **File -> Export To** and choose the file format to create a PDF, PNG, SVG or JPG file of your diagram.

Model Hints and Tips

Navicat provides some useful hints to work on the model more effectively.

Locate Object in the Diagram Canvas

Object selected in the Explorer's Diagram tab will be highlighted in the Diagram Canvas.

Double-click an object in the Explorer's Diagram tab will jump to the corresponding object in the Diagram Canvas.

Delete Object from Model

Select an object in the Diagram Canvas and press SHIFT+DELETE.

Open Table/Entity/View Designer

Double-click a table/entity/view in the Explorer's Model Tab or the Diagram Canvas.

Get Table/View Structure (SQL Statement)

Select and copy a table/view in the Diagram Canvas, and paste it to other text editors.

Design Field without Table/Entity Designer

Select and click a table/entity name and press TAB/DOWN ARROW to add/edit fields. Navicat will predict field types according to field names you entered.

INTEGER/int/int4/NUMBER

- suffix "id", "no" (if it is the first column, it will be predicted as a primary key)
- suffix "num"
- "qty", "number"
- exactly "age", "count"

DECIMAL(10,2)/decimal(10,2)/NUMBER/REAL/money

- suffix "price", "cost", "salary"

FLOAT/double/float8/NUMBER/REAL/float

- "size", "height", "width", "length", "weight", "speed", "distance"

DATE/datetime/date/TEXT/datetime2

- "date", "time"


VARCHAR(255)/varchar(255)/VARCHAR2(255)/TEXT

- other field names


Enter * before the field name to recognize as primary key. e.g. *itemNo:int.

Enter : between field name and field type to custom field type, e.g. itemName:varchar(255).

Reorder Field

Select a table/entity in Diagram Canvas, then press and hold the SHIFT key. Use  to drag the field to a desired location.

Delete Field

Select a table/entity in Diagram Canvas, then press and hold the SHIFT key. Use  to drag the desired field out of the table/entity.

Add Vertex to Foreign Key/Relation/Line/Arrow

Select a foreign key/relation/line/arrow in Diagram Canvas. Press and hold the SHIFT key and click on it to add vertex.

Delete Vertex on Foreign Key/Relation/Line/Arrow

Select a foreign key/relation/line/arrow in Diagram Canvas. Press and hold the SHIFT key and click on the vertex.

Switch to Hand Mode

Press and hold the SPACE key, then move the diagram.

Select a Page in Print Preview

Press and hold the SHIFT key, then point to a page to show the page number.


Press and hold the SHIFT key, then click a page to jump to the corresponding page in Diagram Canvas.


Chapter 9 - Debugger (Available only in Non-Essentials Edition)

About Debugger




Navicat provides two code debuggers: **Oracle PL/SQL Debugger** and **PostgreSQL PL/pgSQL Debugger**. With the debuggers, you can toggle breakpoints, fetch call stacks, view variable values, trace the code, etc.




Oracle PL/SQL Debugger


Oracle PL/SQL Debugger provides step-by-step code debugging for functions, procedures, packages and queries. To launch the debugger, click the  **Debug** button in the designer of the mentioned objects.



You can perform the most commonly used actions for debugging on the toolbar or menu:

Button	Description
 Run	Start running code in debug mode. Enter the Input Parameters if necessary. The debugger executes your code until the end of the code or the next breakpoint is reached. Keyboard shortcut: F9
 Step Over	Resume the execution. The current line will be executed. If the line is a procedure or function call, it will bypass the procedure or function. The counter will then move to the next line of code. Keyboard shortcut: F10
 Step In	Resume the execution. The current line will be executed. If the line is a procedure or function call, the counter goes to the first statement in the procedure or function.

	Otherwise, the counter will move to the next line of code. Keyboard shortcut: F11
 Step Out	Resume the execution. The remaining part of the code within the current procedure or function will be executed. Subsequently, the counter will jump to the line which is just after the caller of the procedure or function. Keyboard shortcut: SHIFT+F11
 Step End	Resume the execution. The counter will jump to the last line of the procedure or function.
 Stop	Stop stepping the code. The execution will stop and cannot resume it.

The **Code** pane shows the code of the procedure or function. You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement. To add a variable to the watch list, right-click the highlighted code and select **Add to Watch List**.

The **Call Stack** pane displays a list of procedures and functions as they are called. To jump to a procedure or function, right-click it and select **Goto Function**.

The **Breakpoints** pane displays all the breakpoints which allowing you to delete, enable or disable breakpoints. To enable/disable a breakpoint, check/uncheck the check box. Also, you can delete a breakpoint or all breakpoints, right-click a breakpoint and select **Remove Breakpoint** or **Remove All Breakpoints**. To jump to the line of a breakpoint, right-click it and select **Goto Function**.


The **Local Variables** pane displays all local variables and their values. Click on a value in the **Value** column to edit. To add a variable to the watch list, right-click it and select **Add to Watch List**.


The **Parameters** pane displays the inputted parameters. To add a parameter to the watch list, right-click it and select **Add to Watch List**.

The **Watch List** pane displays information about the variables being watched, allowing you to add, delete or edit watch variables. To add a watch variable, right-click anywhere on the pane and select **Add Variable**. Then, enter the **Variable Name**. Click on a value in the **Value** column to edit. To delete a watch variable or all watch variables, right-click a variable and select **Remove Variable** or **Remove All Variables**.

The **Log** pane displays the message log when debugging the code and the results after the procedure or function has completed the execution.

PostgreSQL PL/pgSQL Debugger

PostgreSQL PL/pgSQL Debugger provides step-by-step code debugging for PL/pgSQL procedures/functions. To launch the debugger, click the  **Debug** button in the function designer.



You can perform the most commonly used actions for debugging on the toolbar or menu:

Button	Description
Run	Start running code in debug mode. Enter the Input Parameters if necessary. The debugger executes your code until the end of the code or the next breakpoint is reached. Keyboard shortcut: F9
Step Over	Resume the execution. The current line will be executed. If the line is a procedure or function call, it will bypass the procedure or function. The counter will then move to the next line of code. Keyboard shortcut: F10
Step In	Resume the execution. The current line will be executed. If the line is a procedure or function call, the counter goes to the first statement in the procedure or function. Otherwise, the counter will move to the next line of code. Keyboard shortcut: F11
Step Out	Resume the execution. The remaining part of the code within the current procedure or function will be executed. Subsequently, the counter will jump to the line which is just after the caller of the procedure or function. Keyboard shortcut: SHIFT+F11
Stop	Stop stepping the code. The execution will stop and cannot resume it.

The **Code** pane shows the code of the procedure or function. You can add/remove breakpoints for debugging by clicking in the grey area beside each statement.

The **Call Stack** pane displays a list of procedures or functions as they are called.

The **Breakpoints** pane displays all the breakpoints. You can delete a breakpoint or all breakpoints, right-click a breakpoint and select **Remove Breakpoint** or **Remove All Breakpoints**. To jump to the line of a breakpoint, right-click it and select **Goto Function**.


The **Local Variables** pane displays all local variables and their values. Click on a value in the **Value** column to edit.

The **Parameters** pane displays the inputted parameters.

The **Log** pane displays the message log when debugging the code and the results after the procedure or function has completed the execution.

Chapter 10 - Pub/Sub (Available only in Non-Essentials Edition)

About Pub/Sub

Pub/Sub is Publish and Subscribe, allows users to subscribe to channels and receive messages when messages are published to those channels. Users can listen to one or more channels and react to the messages as they come in. In the main window, click  **Pub/Sub** to open the Pub/Sub object list.


Note: Available only for Redis.

You can save the channels you are currently subscribed to as a profile to quickly resume subscriptions when you open the profile.

Hint: Profiles (.npsbredis) are stored under the [Settings Location](#).





Pub/Sub Window





The Pub/Sub Window consists of a toolbar, Channels pane and Messages pane.



① Toolbar

The toolbar of Pub/Sub provides the following functions:

Button	Description
 Subscribe	Subscribe to channels, patterns or shard channels.
 Unsubscribe	Unsubscribe the selected channels.
 Pause	Unsubscribe all channels temporarily.
 Resume	Resume all channels.

 Publish Pane	Toggle a pane for posting a message to a channel.
 Archive Messages	Create an archive file for the current messages.
 Mute	Mute the channels. All new messages will not be received.
 Clear Messages	Clear all messages on the Messages pane.

② Channels Pane

The Channels pane shows all subscribed channels.

③ Messages Pane

The Messages pane shows all messages in the subscribed channels. You can show/hide the messages in different states by right-clicking the grid.

Message texts in different colors indicate:

- Black - Messages sent to a channel
- Grey - System messages
- Blue - Publish / Received messages
- Red - Error messages


④ Message Details Pane

The Message Details pane shows the detailed information of the selected message.


Subscribe Channels

Channels exist on the system only when a subscriber is listening to messages on it, so there is no need to ever create or delete channels.

Subscribe a channel

1. Click  **Subscribe**.
2. You can find out which channels are active on your Redis server. If no active channels, you can customize one.
3. Click **Subscribe**.
4. The subscribed channel appears on the Channels pane.


Publish a message to a channel

1. Click  **Publish Pane**.
2. Choose a channel type and a channel.
3. Enter the message.

- Click **Publish**.


Hint: You can right-click a channel on the Channels pane and select **Publish To** to post messages to that channel.

Archive messages


- Click  **Archive Messages**.
- Enter the file name.
- Click **Save**.

Hint: Archived files (.nrpsbmlog) are stored under the [Settings Location](#). To open the folder, right-click an archived file in the Objects tab and select **Open Containing Folder**.

Hide server messages from a channel

- Click  next to the channel name.


Unsubscribe a channel

- Select a channel on the Channels pane.
- Click  **Unsubscribe**.

Channel Colorings

You can highlight channels by colors for identifying channels and their messages. It lets you instantly know which channel a message is from. The highlighted color displays in the Channels pane and the Messages pane.

To highlight a channel, right-click a channel on the Channels pane and select **Color**.



The screenshot shows the Pub/Sub application window with the following components:

- Menu Bar:** File, Edit, View, Pub/Sub, Window, Help.
- Toolbar:** Save, Subscribe, Unsubscribe, Pause, Publish Pane, Archive Messages, Mute, Clear Messages.
- Channels Pane:** A tree view on the left showing channels: nowChat (green), Temp (blue), Patterns (blue), news.* (red), users.* (blue), and Shard Channels (yellow). Each channel has an eye icon next to it.
- Messages Table:** A table with columns: No., Time, State, Channel, and Message. It lists 12 messages with various states like subscribe, psubscribe, pmessage, ssubscribe, punsubscribe, publish, received, and message.
- Message Detail View:** A pane at the bottom showing details for the first message (No. 1, State: subscribe, Target Channel: Temp, Time: 2023-04-19 11:44:23.845, Message: 1).


Chapter 11 - Data Migration Tools

About Data Migration Tools

Navicat provides a number of powerful tools for working with data, including Import Wizard, Export Wizard, Data Transfer, Data Synchronization, Structure Synchronization, Dump SQL File and Execute SQL File. With those tools, you can migrate your data between different servers, databases and formats easily.

Import Wizard

About Import Wizard

Import Wizard allows you to import data to tables/collections from CSV, TXT, XML, DBF and more. You can save your settings as a profile for future use or setting [automation tasks](#). To open the Import Wizard window, click  **Import Wizard** from the object toolbar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Note: Navicat Essentials edition only supports to import text-based files, such as TXT, CSV, XML and JSON.

Hint: You can drag a supported file to the Table/Collection's Objects tab or a database/schema in the Navigation pane. Navicat will pop up the Import Wizard window automatically. If an existing table/collection is highlighted, Navicat will import the file to the highlighted table/collection. Otherwise, it will import the file to a new table/collection.

Choose File Format

Select one of the available import types for the source file.

Note: The Excel file format is according to the Microsoft Office version installed in your computer.

Choose Source File

Click **Add File(s)** or **Add URL** to add import source files. Select the **Encoding** for the source file.

Note: You can select more than one file to import.

Excel

Sheets will be shown in the **Tables** list.

Access

If there is security settings, i.e. database password and user level security in your access file, you are required to input the necessary information. Click the **Security** button for more settings:

System Database File

Locate the system security file of the Access file, e.g. D:\Temp\Security.mdw.

Database Password

Enter the password for the database if any.

Logon Name

Enter the user name set by the user level security.

Logon Password

Enter the password of that user.

ODBC

Setting up an ODBC Data Source Connection

1. In Control Panel, select **Administrative Tools**.
2. Select **Data Sources (ODBC)**.
3. Click the **Add** button in the **User DSN** tab.
4. Select the appropriate ODBC driver, such as **Microsoft ODBC for Oracle** and click the **Finish** button.
5. Enter the required information.
6. Click the **OK** button to see your ODBC Driver in the list.

Connecting to ODBC Data Source in Navicat

1. Click **Add Data Source**.
2. In the **Provider** tab, select the appropriate ODBC driver, such as **Microsoft OLE DB Provider for ODBC Drivers**.
3. In the **Connection** tab, choose the data source from the **Use data source name** drop-down list and provide valid username and password.
4. All available tables will be included in the **Tables** list if connection is success.

Hint: If you are importing from Access or ODBC, the **Add Query** and **Modify Query** buttons open the **Add Query** dialog where you can construct query to import only certain rows from your source tables. In other words, import only rows that satisfy the criteria set by you. Tables and queries will be shown in the **Tables** list. To delete a query, select it and click the **Delete Query** button.

Choose Delimiter

TXT, CSV

Record Delimiter

Specify the record separator of the file.

Delimited

Import the text file with delimited format.

Fixed Width

Import the text file with fixed-width format. To delimit the source column bounds, click on the desired position to create a break line. Simply drag it to move it or double-click it to remove it.

● Fixed Width - Fields are aligned in columns with spaces between each field

Lines with arrows signify field breaks. To CREATE a break line, click at the desired position. To DELETE a break line, double click on the line. To MOVE a break line, click and drag it.

	10	20	30	40	50
JOB_ID	JOB_TITLE	MIN_SAL			
AC_ACCOUNT	Public Accountant	4200			
AC_MGR	Accounting Manager	8200			
AD_ASST	Administration Assistant	3000			
AD_PRES	President	20000			
AD_VP	Administration Vice President	15000			
FI_ACCOUNT	Accountant	4200			
FI_MGR	Finance Manager	8200			
HR_REP	Human Resources Representative	4000			

Field Delimiter

Specify the field separator.

Text Qualifier

Specify the character that encloses text values.

XML, JSON

Tag that identifies a table row / Tag that identifies a collection row

Define a tag to identify rows.

Consider tag attributes as table field / Consider tag attributes as collection field

For example:

```
<row age="17">
```

```
<id>1</id>
```

```
<name>size</name>
```

```
</row>
```

With this option is on, Navicat will recognize "age" as a field together with "id" and "name", otherwise, only "id" and "name" will be imported as fields.

Note: Navicat does not support multiple level of XML file.

Choose Additional Options

The following options depend on the file format chose in the first step.

Field Name Row

Indicate which row should Navicat recognize as field names.

First Data Row

Indicate which row should Navicat start reading the actual data.

Last Data Row

Indicate which row should Navicat stop reading the actual data.

Note: If no field names are defined for the file, enter 1 for First Data Row and 0 for Field Name Row.

Date Order, Date Delimiter

Specify the format for date and the date separator.

Time Delimiter

Specify the time separator.

Decimal Symbol

Specify the decimal separator for decimal number.

Date Time Order

Specify the order of date and time.

Binary Data Encoding

Set binary data are imported as Base64 encoded or no encoding in the file.

Choose Target Table / Collection

You are allowed to define a new name or choose to import into an existing table/collection from the drop-down list.

Note: If you type a new name in **Target Table / Target Collection**, the box in **New Table / New Collection** will be checked automatically.

Source Table	Target Table	New Table
jobs_fixed	jobs	<input checked="" type="checkbox"/>

For importing multiple tables/collections, all tables/collections will be shown in the list.

Source Table	Target Table	New Table
countries	countries	<input type="checkbox"/>
duty_time	duty	<input checked="" type="checkbox"/>
employees	employees	<input type="checkbox"/>
job_history	job_history	<input type="checkbox"/>
jobs	jobs	<input type="checkbox"/>

Adjust Field Structures and Map Fields

Navicat will make assumption on the field types and length in the source table/collection. You are allowed to choose desired type from the drop-down list.

Hint: For importing multiple tables/collections, select other tables/collections from the **Source Table / Source Collection** drop-down list.

Source Table: duty_time

Target Table: duty

	Source Field	Target Field	Type	Length	Scale	Primary Key
<input checked="" type="checkbox"/>	ID	ID	int	0	0	
<input checked="" type="checkbox"/>	EMPLOYEE_ID	EMPLOYEE_ID	double	0	0	
<input checked="" type="checkbox"/>	ON_DUTY	ON_DUTY	tinyint	0	0	
<input checked="" type="checkbox"/>	OFF_DUTY	OFF_DUTY	int	0	0	

If you are importing data into existing tables/collections, you might need to map the source field names manually to the target, or right-click and select **Smart Match All**, **Direct Match All** and **Unmatch All** from the pop-up menu for quick mapping.

Source Field	Target Field	Primary Key
EMPLOYEE_ID		
FIRST_NAME		
LAST_NAME		
EMAIL		
PHONE_NUMBER		
HIRE_DATE		
JOB_ID		
SALARY		
COMMISSION_PCT		

Source Field	Target Field	Primary Key
EMPLOYEE_ID		
FIRST_NAME		
LAST_NAME		
EMAIL		
PHONE_NUMBER		
HIRE_DATE		
JOB_ID		
SALARY		

If you are importing via ODBC, the **Condition Query** button opens the **WHERE** dialog where you can specify a *WHERE* clause to import only certain rows from the source. In other words, import only rows that satisfy the criteria set by you.

Hint: Do not include the word *WHERE* in the clause.

Choose Import Mode

Select the import mode that defines how the data being imported.

Import Mode:

- ☒ Append: add records to the destination table
- ☐ Update: update records in the destination with matching records from source
- ☐ Append/Update: if records exist in destination, update it. Otherwise, add it
- ☐ Delete: delete records in destination that match records in source
- ☐ Copy: delete all records in destination, repopulate from the source

Hint: To activate the remaining options, you must enable Primary Key in the previous step.

Source Field	Target Field	Primary Key
<input checked="" type="checkbox"/> EMPLOYEE_ID	EMPLOYEE_ID	<input checked="" type="checkbox"/>
FIRST_NAME	FIRST_NAME	
LAST_NAME	LAST_NAME	
EMAIL	EMAIL	
PHONE_NUMBER	PHONE_NUMBER	
HIRE_DATE	HIRE_DATE	
JOB_ID	JOB_ID	

Click the **Advanced** button for more settings. The following options depend on the connection server type.

Run multiple queries in each execution

Execute multiple SQL statements at once, which will make the import process faster.

Use extended insert statements

Insert records using extended insert syntax.

Example:

```
INSERT INTO `users` VALUES ('1', 'Peter McKindy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');
```

Use empty string as NULL

Import NULL value if the source data field contains empty string.

Ignore foreign key constraint

Ignore the checking of foreign key constraints during the import process.

Continue on error

Ignore errors that are encountered during the import process.

Include Unique, Index and Foreign Key

Include uniques, indexes and foreign keys during the import process.

Note: Support only when the file type is MS Access database or ODBC.

Create Auto Increment Fields

Create auto increment fields during the import process.

Note: Support only when the file type is MS Access database, Paradox file or DBase file.

Import Deleted Records

Import the deleted records in the DBase file during the import process.

Note: Support only when the file type is DBase file.

Save and Start Import


Click the **Start** button to begin the import process. The wizard will display the import progress, execution time, and success or failure messages.

After the import process finished, you can click the **Log** button to open the log file.

Hint: Click the **Save** button to save your settings as a profile.

Export Wizard

About Export Wizard

Export Wizard allows you to export data from tables, collections, views, or query results to any available formats. You can save your settings as a profile for future use or setting [automation tasks](#). To open the Export Wizard window, click  **Export Wizard** from the object toolbar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Note: Navicat Essentials edition only supports to export text-based files, such as TXT, CSV, HTML, XML, SQL and JSON.

Choose File Format

Select one of the available export formats for the target file.


Note: The Excel file format is according to the Microsoft Office version installed in your computer. Navicat 64-bit version does not support exporting to .mdb file.

Choose Saving Path

You can set the exported file name and location in this step.

Check the box next to the object name that you want to export. If an existing object is highlighted in the object pane, it will be checked automatically and assigned a default file name and location. The file extension in the **Export to** text box changes according to the selected export type in the first step.

Note: For exporting query results, ensure the query is saved before running Export Wizard. Otherwise, no source object displayed in here.



Select All Button	Description
Select All / Unselect All	Select / unselect all source objects.
Export selected to same file	Export the selected objects into the same target file. When the file format is Excel, each object will be exported as a sheet in the Excel file.
Export selected to same folder	Export the selected objects into the same directory.

Advanced Button	Description
Encoding	Select the encoding for the exported file.
Add timestamp	Check this option if you want your file name specifies the timestamp of the export is run. Select the date/time format from the drop-down menu.

Choose Columns / Fields for Export

You can select what fields to export. All the fields are selected in the list by default. If you want to omit some fields to be exported, uncheck the **All Fields** option first and then uncheck those fields in the list.

Note: For exporting query result, the wizard will skip this step.

Choose Additional Options

The following options depend on the file format chose in the first step.

Include column titles

Field names will be included into the exported file if this option is on.

Blank if zero

Leave it blank if the field content is 0.

Append

Append records to the existing file

Continue on error

Ignore errors that are encountered during the export process.

Use Attributes Format in XML

Attributes Format
<pre><RECORDS> <RECORD OrderNo="1003" ItemNo="1" PartNo="1313" Qty="5" Discount="0"></RECORD> <RECORD OrderNo="1004" ItemNo="1" PartNo="1313" Qty="10" Discount="50"></RECORD> </RECORDS></pre>
Non-Attributes Format
<pre><RECORDS> <RECORD> <OrderNo>1003</OrderNo> <ItemNo>1</ItemNo> <PartNo>1313</PartNo> <Qty>5</Qty> <Discount>0</Discount> </RECORD> <RECORD> <OrderNo>1004</OrderNo> <ItemNo>1</ItemNo> <PartNo>1313</PartNo></pre>

```
<Qty>10</Qty>
<Discount>50</Discount>
</RECORD>
</RECORDS>
```

Export as legacy format (with "RECORDS" key)

Legacy Format

```
{
  "RECORDS": [
    {
      "COUNTRY_ID": AR
      "COUNTRY_NAME": "Argentina"
      "REGION_ID": 2
    },
    {
      "COUNTRY_ID": AU
      "COUNTRY_NAME": "Australia"
      "REGION_ID": 3
    }
  ]
}
```

New Format

```
[
  {
    "COUNTRY_ID": AR
    "COUNTRY_NAME": "Argentina"
    "REGION_ID": 2
  },
  {
    "COUNTRY_ID": AU
    "COUNTRY_NAME": "Australia"
    "REGION_ID": 3
  }
]
```

Record Delimiter, Field Delimiter, Text Qualifier

Specify the record separator, the field separator and the character that encloses text values.

Zero padding date

Add a leading zero to pad days and months to two digits if necessary.

Date Order, Date Delimiter

Specify the format for date and the date separator.

Time Delimiter

Specify the time separator.

Decimal Symbol

Specify the decimal separator for decimal number.

Binary Data Encoding

Set binary data are exported as Base64 encoded or no encoding in the file.

Save and Start Export

Click the **Start** button to begin the export process. The wizard will display the export progress, execution time, and success or failure messages.

After the export process finished, you can click the **Open** button to open the exported file or the log file.

Hint: Click the **Save** button to save your settings as a profile.

Data Transfer (Available only in Non-Essentials Edition)

About Data Transfer

Navicat allows you to transfer objects from one database/schema to another, or to a sql file (RDBMS) or a Javascript file (MongoDB). The target database and/or schema can be on the same server as the source or on another server. To open the Data Transfer window, choose **Tools -> Data Transfer** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.


Hint: Profiles are saved under the [Profiles Location](#).

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Hint: You can drag tables/collections to a database/schema in the Navigation pane. If the target database/schema is within the same connection, Navicat will copy the tables/collections directly. Otherwise, Navicat will pop up the Data Transfer window.

Choose Connections & Advanced Options (Step 1)

Choose Source and Target Connections

In the Data Transfer window, define connections, databases and/or schemas for **Source Database** and **Target Database**. You can click  to swap the source and target settings.

You can also transfer your selected database objects directly to a text file. Select the **File** option. Choose the target path, **SQL Format** and **Encoding** for the file.

Note: Navicat Premium supports transferring table with data across different server types, e.g. from MySQL to Oracle. If the source connection is MongoDB, Navicat Premium only can transfer data to MongoDB server.

Choose Advanced Options

Then, click the **Options** button to set the advanced options. The options depend on the source and target connection server types and sort in ascending order.

Continue on error

Ignore errors that are encountered during the transfer process.

Convert object name to

Check this option if you require convert object names to **Lower case** or **Upper case** during the process.

Create collections

Check this option if you want to create collections in the target database. Suppose this option is unchecked and collections already exist in the target database, then all data will be appended to the destination collections.

Create records

Check this option if you require all records to be transferred to the destination database and/or schema.

Create tables

Check this option if you want to create tables in the target database. Suppose this option is unchecked and tables already exist in the target database/schema, then all data will be appended to the destination tables.

Create target database/schema if not exist

Create a new database/schema if the database/schema specified in the target server does not exist.

Drop target objects before create

Check this option if database objects already exist in the target database and/or schema, the existing objects will be deleted once the data transfer starts.

Drop with CASCADE

Check this option if you want to drop the dependent database objects with the cascade option.

Include auto increment

Include auto increment in the table with this option is on.

Include character set

Include character set in the table with this option is on.

Include checks

Include checks in the table with this option is on.

Include definers

Include the definers of the objects with this option is on.

Include engine/table type

Include table type with this option is on.

Include excludes

Include exclusion constraints in the table with this option is on.

Include foreign key constraints

Include foreign keys in the table with this option is on.

Include indexes

Include indexes in the table with this option is on.

Include other collection options

Include other options in the collection with this option is on.

Include other table options

Include other options in the table with this option is on.

Include owners

Include the owners of the objects with this option is on.

Include rules

Include rules in the table with this option is on.

Include triggers

Include triggers in the table with this option is on.

Include uniques

Include uniques in the table with this option is on.

Lock source tables

Lock the tables in the source database and/or schema during the data transfer process.

Lock target tables

Lock the tables in the target database and/or schema during the data transfer process.

Use complete insert statements

Insert records using complete insert syntax.

Example:

```
INSERT INTO `users` (`ID Number`, `User Name`, `User Age`) VALUES ('1', 'Peter McKindy', '23');
```

```
INSERT INTO `users` (`ID Number`, `User Name`, `User Age`) VALUES ('2', 'Johnson Ryne', '56');
```

```
INSERT INTO `users` (`ID Number`, `User Name`, `User Age`) VALUES ('0', 'katherine', '23');
```

Use DDL from SHOW CREATE TABLE

If this option is on, DDL will be used from SHOW CREATE TABLE.

Use DDL from sqlite_master

If this option is on, DDL will be used from the SQLITE_MASTER table.

Use delayed insert statements

Insert records using DELAYED insert SQL statements.

Example:

```
INSERT DELAYED INTO `users` VALUES ('1', 'Peter McKindy', '23');
```

```
INSERT DELAYED INTO `users` VALUES ('2', 'Johnson Ryne', '56');
```

```
INSERT DELAYED INTO `users` VALUES ('0', 'katherine', '23');
```

Use extended insert statements

Insert records using extended insert syntax.

Example: *INSERT INTO `users` VALUES ('1', 'Peter McKindy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');*

Use hexadecimal format for BLOB

Insert BLOB data as hexadecimal format.

Use single transaction

Check this option if you want to use a single transaction during the data transfer process.

Use transaction

Check this option if you want to use transaction during the data transfer process.

Choose Objects & Transfer Mode (Step 2)

Choose Objects to Transfer

All database objects are unselected in the **Database Objects** list by default. Check the database objects that you want to transfer.

Database Objects

- ▼ **Tables (15/17)**
 - ☐ All tables during execution (*)
 - > ☐ Custom (15/17)
- ▼ **Views (3/8)**
 - ☐ All views during execution (*)
 - ▼ **Custom (3/8)**
 - ☐ actor_full_name
 - ☒ actor_info
 - ☐ customer_list
 - ☒ film_list (Advanced)
 - ☐ nicer_but_slower_film_list
 - ☒ sales_by_film_category
 - ☐ sales_by_store
 - ☐ staff_list
- ▼ **Function (*)**
 - ☒ All functions during execution (*)
 - > ☐ Custom (0/8)
- ▼ **Event (*)**
 - ☒ All events during execution (*)
 - > ☐ Custom (0/2)

Transfer Mode:

☐ Auto ☒ Advanced

Target Name:

☒ Transfer as table

☐ Number of rows per batch:

All <objects> during execution (*)	All the database objects being transferred to the target database/schema, all newly added database objects will also be transferred without amending the data transfer profile.
Custom	Only the checked database objects will be transferred. However, if you add any new database objects in the source database and/or schema after you create your data transfer profile, the newly added database objects will not be transferred unless you manually modify the Database Objects list.

Choose Transfer Mode for Tables / Views

You can customize the **Transfer Mode** for the selected table/view. If you choose **Auto**, Navicat will transfer the table/view using the default settings. If you want to customize the transfer settings, choose **Advanced** and set the following options:

Option	Description
Target Name	Enter the name of the table / view that will be created in the target database.
All fields	Transfer all fields in the table.

Custom fields	You can choose which fields to transfer. Click + and select the fields. Change the name of the target field if necessary.
All rows	Transfer all records in the table.
Number of rows per batch	Specify the number of rows of data per batch. If it is not enabled, all data in the table is sent to the target server as a single transaction.
Custom recordsets	Filter the records for transfer. Click + and enter an expression.
Recordset Generator	If your table is large, you may want to divide it to several record sets to avoid connection timeout. The Recordset Generator can divide the records into a number of recordsets as evenly as possible between the start and end values of a field. Set Field Name , Start Value , End Value and Number of Recordsets in the pop-up window.
SQL Preview	Show the SQL statements for returning the recordsets.
Use transaction for each recordset	Use a transaction for each recordset during the data transfer process.
Transfer as table	The view will be transferred to the target database as a new table.

Confirm & Start Data Transfer (Step 3)

A summary table lists all selected objects that is being transferred to the target database.

Summary

15 tables, 3 views, All functions, All events

Source Object	Target Object	Mode
actor	actor	Auto
category	category	Auto
city	city	Auto
country	country	Auto
film	film	Advanced (All fields, All rows, Number of rows per batch: 1000)
film_actor	film_actor	Auto
film_category	film_category	Auto
film_text	film_text	Auto
inventory	inventory	Auto
language	language	Advanced (Custom fields, All rows)
payment	payment	Auto
rental	rental	Auto
sales	sales	Auto
staff	staff	Auto

☐ Continue on error

☒ Drop target objects before create

Continue on error

Ignore errors that are encountered during the transfer process.

Drop target objects before create

Check this option if database objects already exist in the target database and/or schema, the existing objects will be deleted once the data transfer starts.

Start Data Transfer

Click the **Start** button to execute the data transfer process. The window will display the execution progress, execution time, and success or failure messages.

Data Synchronization (Available only in Non-Essentials Edition)

About Data Synchronization

Navicat allows you to transfer data from one database and/or schema to another with detailed analytical process. In other words, Navicat provides the ability for data in different databases and/or schemas to be kept up-to-date so that each repository contains the same information. To open the Data Synchronization window, choose **Tools -> Data Synchronization** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.


Hint: Profiles are saved under the [Profiles Location](#).

Note: SQL Server 2000 does not support this feature. For Oracle server, BLOB, CLOB, NCLOB, LONG and LONG RAW data are skipped during the data synchronization process. TIMESTAMP primary key cannot synchronize (insert, update) with Database Link to 9i server. RAW primary key cannot synchronize (insert, update, delete) with Database Link to any server, without error.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB. Navicat Premium and Navicat for MySQL support synchronizing between MySQL and MariaDB.

Choose Connections & Comparing Options (Step 1)

Choose Source and Target Connections

In the Data Synchronization window, define connections, databases and/or schemas for **Source Database** and **Target Database**. You can click  to swap the source and target settings.

Choose Comparing Options

Then, click the **Options** button to set the comparing options.

Insert records

Insert records if the records do not exist in the target.

Delete records

Delete extra records from the target.

Update records

Update the target if the record is different from the source.

Choose Table / Collection Mapping (Step 2)


In this step, only tables/collections which contain identical names between the source and target are mapped in the list by default. If you do not want some tables/collections to be synchronized, disable them manually from the drop-down list.

Keys and fields which contain identical names are also mapped. You can change the mapping in the **Key Mapping** and **Field Mapping** columns.

After mapping the tables/collections, click **Compare & Preview** to view the comparison results (Step 3). If you want to skip the preview and deploy immediately, click **Compare & Deploy**.

View Data Comparison Results (Step 3)

After comparing data, the window shows the number of records that will be inserted, updated or deleted in the target. Uncheck the **Show identical table and others** / **Show identical collection and others** option to hide the tables/collections with identical data and the tables/collections with different structures. All tables/collections with different data and all actions are checked by default. Uncheck the checkbox that you do not want to apply to the target.



Source Table	Target Table	Insert	Update	Delete	Same	Message
<input checked="" type="checkbox"/> actor	actor	<input type="checkbox"/> 0	<input checked="" type="checkbox"/> 3	<input type="checkbox"/> 0	<input type="checkbox"/> 197	
<input checked="" type="checkbox"/> address	address	<input type="checkbox"/> 0	<input checked="" type="checkbox"/> 11	<input type="checkbox"/> 0	<input type="checkbox"/> 592	
<input type="checkbox"/> category	category	<input type="checkbox"/> 0	<input type="checkbox"/> 0/1	<input type="checkbox"/> 0	<input type="checkbox"/> 15	
<input checked="" type="checkbox"/> country	country	<input type="checkbox"/> 0	<input checked="" type="checkbox"/> 1	<input type="checkbox"/> 0	<input type="checkbox"/> 108	
<input type="checkbox"/> customer	customer	<input type="checkbox"/> 0	<input type="checkbox"/> 4/599	<input type="checkbox"/> 0	<input type="checkbox"/> 0	
<input checked="" type="checkbox"/> film	film	<input type="checkbox"/> 0	<input checked="" type="checkbox"/> 11	<input type="checkbox"/> 0	<input type="checkbox"/> 989	
<input type="checkbox"/> film_text	film_text	<input type="checkbox"/> 0	<input type="checkbox"/> 1/2	<input checked="" type="checkbox"/> 1	<input type="checkbox"/> 997	
<input checked="" type="checkbox"/> payment	payment	<input type="checkbox"/> 0	<input checked="" type="checkbox"/> 1	<input type="checkbox"/> 0	<input type="checkbox"/> 16048	
<input checked="" type="checkbox"/> rental	rental	<input type="checkbox"/> 0	<input checked="" type="checkbox"/> 3	<input type="checkbox"/> 0	<input type="checkbox"/> 16041	
<input checked="" type="checkbox"/> store	store	<input checked="" type="checkbox"/> 1	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 2	
<input type="checkbox"/> city	city	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 600	
<input type="checkbox"/> film_actor	film_actor	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 5462	
<input type="checkbox"/> film_category	film_category	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 0	<input type="checkbox"/> 1000	

When you selected a table/collection in the list, the bottom pane shows data in the source and target. Values that differ between the source and target are highlighted. To view multiple lines data, right-click the grid and select **Show Assistant Viewer**. Uncheck the records that you do not want to apply to the target.

Choose an option from the drop-down list to show the data.

Option	Description
Difference	Show all records that are different in the source and target.
Insert	Only show the records that do not exist in the target.
Update	Only show the records that exist in both source and target, but they have different values.
Delete	Only show the records that do not exist in the source.
Same	Show the records that exist in both source and target and they have identical values.
All Rows	Show all records in the source and target.

Difference					
payment			payment		
staff_id	rental_id	amount	staff_id	rental_id	amount
1	76	2.99	1	7	1.10
1	1185	5.99	1	1185	6.99
2	2363	0.99	2	2363	1.99
2	11299	3.99	2	11299	2.99
1	11367	0.99	1	11367	4.99


Click the **Next** button to show the scripts of all selected tables/collections and records.

Edit & Execute Selected Scripts (Step 4)

You can view all scripts that will be executed in the target database in the **Deployment Script** tab.

Deployment Options Button	Description
Deployment Options	<p>Continue on error - Ignore errors that are encountered during the execution process if necessary.</p> <p>Run multiple queries in each execution - Execute multiple SQL statements at once, which will make the transfer synchronization faster.</p> <p>Use transaction - Rollback all data when error occurs.</p>
Edit Script	Open the Edit Deployment Script window to rearrange the order of the scripts.
Copy Script to Clipboard	Copy all scripts from the Deployment Script tab to the clipboard.
Open Script in Query Editor	Open a new query window and display the scripts.

In the **Edit Deployment Script** window, use the arrow buttons to move the scripts.



Then, click the **Start** button to execute the scripts. The window will display the execution progress, execution time, and success or failure messages.

Structure Synchronization (Available only in Non-Essentials Edition)

About Structure Synchronization

Navicat allows you to compare and modify the table structures and other objects with detailed analytical process. In other words, Navicat compares objects between two databases and/or schemas and states the differential in structure. To open the Structure Synchronization window, choose **Tools -> Structure Synchronization** from the menu bar.


You can save your settings as a profile for future use. To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the [Profiles Location](#).

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB. Navicat Premium and Navicat for MySQL support synchronizing between MySQL and MariaDB.

Choose Connections & Comparing Options (Step 1)

Choose Source and Target Connections

In the Structure Synchronization window, define connections, databases and/or schemas for **Source Database** and **Target Database**. You can click  to swap the source and target settings.

Choose Comparing Options

Then, click the **Options** button to set the database/schema comparing options. The options depend on the connection server type and sort in ascending order.

Compare auto increment value

Check this option if you want to compare the auto increment values of tables.

Compare character set

Check this option if you want to compare the character sets of tables.

Compare checks

Check this option if you want to compare checks.

Compare collation

Check this option if you want to compare the collations of tables.

Compare definers

Check this option if you want to compare the definers.

Compare events

Check this option if you want to compare events.

Compare excludes

Check this option if you want to compare table excludes.

Compare foreign keys

Check this option if you want to compare table foreign keys.

Compare functions

Check this option if you want to compare functions.

Compare identity last value

Check this option if you want to compare the identity last values of tables.

Compare indexes

Check this option if you want to compare indexes.

Compare owners

Check this option if you want to compare the owners of the objects.

Compare partitions

Check this option if you want to compare table partitions.

Compare primary keys

Check this option if you want to compare table primary keys.

Compare rules

Check this option if you want to compare rules.

Compare sequences

Check this option if you want to compare sequences.

Compare storage

Check this option if you want to compare table storages.

Compare table options

Check this option if you want to compare other table options.

Compare tables

Check this option if you want to compare tables.

Compare tablespace and physical attributes

Check this option if you want to compare tablespace and physical attributes.

Compare triggers

Check this option if you want to compare triggers.

Compare uniques

Check this option if you want to compare table uniques.

Compare views

Check this option if you want to compare views.

Drop with CASCADE

Check this option if you want to drop the dependent database objects with the CASCADE option.

Identifier Case Sensitivity


Ignore or consider the case of identifiers when mapping, or use the server default setting.

Start Comparison

Click the **Compare** button to compare the source and target databases.

View Structure Comparison Results (Step 2)

After comparing structures, the tree view shows the differences between the source and target databases or schemas. All objects are checked in the tree view by default. Uncheck the objects you do not want to apply to the target. You can expand the table objects to view the detailed structure.



You can choose to group the objects in the tree views by object types or operations by selecting **Group by object type** or **Group by operation**.

Operation	Description
→	Object exists in both source and target databases/schemas, but they have different definition. The target object will be modified based on the source object.
+	Object does not exist in the target database/schema. It will be created in the target.
×	Object does not exist in the source database/schema. The target object will be deleted.
=	Object exists in both source and target databases/schemas and they have identical definition. No operation will be applied.

When you selected an object in the tree view, the **DDL Comparison** tab shows the DDL statements of that object in the source and the target, and the **Deployment Script** tab shows the detailed SQL statements of the object that will be executed in the target databases.


Click the **Next** button to show the scripts of all selected objects.

Edit & Execute Selected Scripts (Step 3)

You can view all scripts that will be executed in the target database in the **Deployment Script** tab.

Deployment Options Button	Description
Deployment Options	Continue on error - Ignore errors that are encountered during the execution process if necessary.
Edit Script	Open the Edit Deployment Script window to rearrange the order of the scripts.
Copy Script to Clipboard	Copy all scripts from the Deployment Script tab to the clipboard.
Open Script in Query Editor	Open a new query window and display the scripts.

In the **Edit Deployment Script** window, use the arrow buttons to move the scripts.



Then, click the **Start** button to execute the scripts. The window will display the execution progress, execution time, and success or failure messages.

Dump & Execute SQL / Script File

The **Dump SQL File**, **Execute SQL File**, **Dump Script File** and **Execute Script File** features allow you to dump your database, schema, tables or collections to a SQL or .js file or execute SQL or .js files in your connection, database or schema.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

To dump a file

1. In the main window, right-click an opened database/schema or right-click the selected tables/collections, and select **Dump SQL File** or **Dump Script File** -> **Structure Only** or **Structure And Data**.

2. Browse the save location and enter a file name.

3. Click **Save**.

Hint: After the dump process finished, you can click the **Open** button to open the file using Query Editor.

To execute a file

1. In the main window, right-click an opened connection, database or schema and select **Execute SQL File** or **Execute Script File**.
2. Browse your SQL or .js file, choose the encoding of the file and enable appropriate options.

Option	Description
Continue on error	Ignore errors that are encountered during the execution process.
Run multiple queries in each execution	Execute multiple SQL statements at once, which will make the execution process faster.
SET AUTOCOMMIT=0 / No Auto Commit	Disable auto commit mode.

3. Click **Start**.

Hint: You can drag and drop a .sql or .js file to an opened connection, database or schema in the Navigation pane. Navicat will pop up the Execute SQL File or Execute Script File window automatically.

Execute Command File

The **Execute Command File** feature allow you to execute Redis command file (.redis) in your connection or database.

Note: Available only for Redis.

To execute a file

1. In the main window, right-click an opened connection or database and select **Execute Command File**.
2. Browse your .redis file, choose the encoding of the file and enable appropriate options.

Option	Description
Batch Size	Specify the maximal number of commands in a batch.
Continue on error	Ignore errors that are encountered during the execution process.

3. Click **Start**.

Hint: You can drag and drop a .redis file to an opened connection or database in the Navigation pane. Navicat will pop up the Execute Command File window automatically.

MongoImport & MongoExport

About MongoImport & MongoExport

MongoDB provides two utilities for import and export data: MongoImport and MongoExport. You can import or export the data according to the specified conditions.

MongoImport

MongoImport allows you to import data from a JSON, CSV or TSV file into MongoDB database.

Note: You must have [mongoimport](#) executable for this feature to work.

To import a file

1. In Navicat main window, right-click your database and select **MongoImport**.
2. In the **General** and **Advanced** tabs, select the input file path, the target collection, the file type, and the appropriate import options.
3. Click the **Start** button to begin the import process. The **Message Log** tab will display the import progress, execution time, and success or failure messages.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the [Profiles Location](#).

MongoExport

MongoExport allows you to export MongoDB collections to a JSON or CSV file.

Note: You must have [mongoexport](#) executable for this feature to work.

To export collections

1. In Navicat main window, right-click your database and select **MongoExport**.
2. In the **General** and **Advanced** tabs, select the export file path, the source collection, the file type, and the appropriate export options.
3. Click the **Start** button to begin the export process. The **Message Log** tab will display the export progress, execution time, and success or failure messages.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the [Profiles Location](#).

Chapter 12 - Data Generation (Available only in Non-Essentials Edition)

About Data Generation

With the column-intelligent data generation, you can populate selected tables with realistic and meaningful test data. The generated data in one column is based on the data in another. You can populate empty tables, or add extra rows to your existing tables, and control over the creation of the foreign key data. To open the Data Generation window, choose **Tools -> Data Generation** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the [Profiles Location](#).

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Choose Target Connection (Step 1)

Choose Target Connection

In the Data Generation window, define the target connection, database and/or schema.

Choose Advanced Options

Then, click the **Options** button to set the advanced options. The options depend on the target connection server type and sort in ascending order.

Continue on error

Ignore errors that are encountered during the data generation process.

Empty collections before generating data

Remove all data in the target collections before generating data.

Empty tables before generating data

Remove all data in the target tables before generating data.

Run multiple insert statements

Execute multiple INSERT statements at once, which will make the execution process faster.

Use extended insert statements

Insert records using extended insert syntax.

Example: *INSERT INTO `users` VALUES ('1', 'Peter McKindy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');*


Use transaction

Check this option if you want to use transaction during the data generation process.

Choose Objects & Column Properties (Step 2)

Choose Objects to Populate

All tables are unselected in the Database Objects list by default. Check the tables and columns that you want to populate.



You can copy all the settings from one object and paste the settings to other objects by right-clicking an object in the list.

Choose Table / Collection Properties

You can specify the volume of the data you want to generate for each table/collection.

Navicat did not take dependencies into account when defining the order in which tables/collections data will be generated. Click the **Table Generation Order/Collection Generation Order** button to change the order if necessary.

Choose Column Properties

Navicat automatically assigns a generator to each column based on its table name, column name, data type, and length. Use the **Generator** combo box to select a generator from the list.

The following table shows the common properties.

Option	Description
Include default values	Generate default values. You can set the default value of the column, and set the Percentage of the default values in the column.
Include null values	Generate NULL values. You can set the Percentage of Null values in the column.
Set unique	Make the values generated for the column unique.
Convert value to	Convert the values to lower case, upper case or proper case (the first letter in each word is capitalized, the other letters are lower case).
Disable data linkage between fields	Unlink the data between this field with other fields. If this option is unchecked, Navicat will generate data with linkage between fields. Example: If the name field is "Robert Rose", the email field will be like "robertrose@outlook.com".

Use Generator (Step 2.1)

Number Generator

The Number Generator generates numeric values such as integers and decimal numbers.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Start	Specify the minimum numeric value.
End	Specify the maximum numeric value.
Number Type	Choose the type of the numeric values: Integer or Decimal Number.

Date / Time / DateTime Generator

The Date / Time / DateTime Generator generates dates and/or times.

Generator Properties

You can customize the generator by changing its properties. The properties depend on the generator you are chosen.

Option	Description
Start Date	Specify the minimum date value.
End Date	Specify the maximum date value.
Whole Day	Include any time of the day.
Start Time	Specify the minimum time value.
End Time	Specify the maximum time value.
Day of the Week	Choose the day of the week for the date value.

Sequence Generator

The Sequence Generator generates randomized sequences of integers.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Start	Specify first number in the sequence.
Increment	Specify the value added to the current sequence value to create a new value.
Min	Specify the lower bound of the sequence range.
Max	Specify the upper bound of the sequence range.
Cycle	The sequence continues to generate values after reaching either its maximum or minimum value.

Enum Generator

The Enum Generator generates values from specified value list.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Values	Specify the values. Values are generated from the existing data of the column, where applicable.

Text Generator

The Text Generator generates dummy text values.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Number of Characters	Specify the minimum and maximum number of characters.

Image/Binary Generator

The Image/Binary Generator generates images and Binary data, or randomly imports files in a specified folder.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Image Generator	
Image Width	Specify the width of the image.
Image Height	Specify the height of the image.
Image Format	Choose the image file format.
Randomly Pick From Folder	
Folder Path	Specify a folder containing a number of images or binary data files.
Filter with Extensions	Specify the extension list for the files that are being imported.

Foreign Key Generator

The Foreign Key Generator generates foreign key values for a child table field based on the values contained in a parent table field.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Schema	Choose the schema of the parent table.
Table	Choose a parent table.
Field	Choose a field in the parent table. Make sure that the child table column and the parent table column have compatible types.
Generation Mode	Choose the generation mode of the data: random data, no repeated data or specified number of repetitions.

UUID Generator

The UUID Generator generates a set of universally unique identifiers (UUIDs) based on the specified format.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
UUID Format	Generate UUIDs with or without hyphens.
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

Regular Expression Generator

The Regular Expression Generator generates values based on a regular expression.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regular Expression	Enter the regular expression.

Syntax Elements

The following table shows the syntax elements.

Description	Example	Generates
Basic		
ordinary chars	Kelly	Kelly
individual chars	[AB]	A or B
initial] in char set	[]]
[x-y] range	[0-9]	e.g. 2 or 7
[chars] character set	[A-Z0-9]	e.g. 3 or M
[exclude chars] character set	[^abc]	e.g. m or [
* zero or more	abc*	e.g. abcc or ab
+ 1 or more	abc+	e.g. abcccc or abc
? Include or not	abc?	ab or abc
(regexp) grouping	(abc)*d	e.g. abcabacd or d
{num} repeat	b{4}	bbbb
{min,max} repeat	b{3,4}	bbb or bbbb
{min,} at least min repeats	b{4,}	e.g. bbbb or bbbbbbbbb
() empty string	()	
alternatives	True False	True or False
empty alternative	th(e is at)	e.g. the or that
Escapes		
backslash	\\	\
dot	\.	.
caret	\^	^
dollar sign	\\$	\$
left curly bracket	\{	{
right curly bracket	\}	}
left square bracket	\[[
right square bracket	\]]
left parenthesis	\((
right parenthesis	\))
vertical bar	\\	
asterisk	*	*
plus mark	\\+	+
question mark	\\?	?
upper or lower-case letter or underscore or	\\w	[A-Za-z_0-9]

digit		
all ASCII printable characters	\W	[-~]
digit	\d	[0-9]
carriage return	\r	
tab character	\t	
space character	\s	

Name Generator

The Name Generator generates first, last or full names in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Format Type	Generate first names, last names or full names.
Languages	Select the language of the names.

Gender Generator

The Gender Generator generates different genders in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the genders.

Title Generator

The Title Generator generates different titles in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the titles.

Marital Status Generator

The Marital Status Generator generates different marital status types in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the marital status.

Phone Number Generator

The Phone Number Generator generates random phone numbers which follow the phone number rules.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Format	Choose the format of the phone numbers. If you choose to generate international phone numbers, the country code will be added.
Include delimiters	Add delimiters to the phone numbers.
Regions	Select the region of the phone numbers.

Email Generator

The Email Generator generates emails with the specified domain names.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Domains	Enter a list of email domain names.

Job Title Generator

The Job Title Generator generates different job titles in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the job titles.

Social Network ID Generator

The Social Network ID Generator generates random social network account names.

Payment Method Generator

The Payment Method Generator generates payment methods from specified value list.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Values	Specify the payment methods.

Credit Card Type Generator

The Credit Card Type Generator generates types of credit cards.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Types	Select the credit card types.

Credit Card Number Generator

The Credit Card Number Generator generates credit card numbers for different credit card types.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Types	Select the credit card type.

Credit Card Date Generator

The Credit Card Date Generator generates the issuance dates or expiration dates of credit cards.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Date Type	Generate issuance dates or expiration dates.
Date Range	Choose the date range (MM/YY - MM/YY).

Company Name Generator

The Company Name Generator generates company names in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the company names.

Department Generator

The Department Generator generates company department names in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the department names.

Industry Generator

The Industry Generator generates industry names in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the industry names.

Address Generator

The Address Generator generates line 1, line 2 or full addresses of US, UK, China or Japan.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Type	Generate line 1, line 2 or full addresses.
Regions	Select the region of the addresses.

City Generator

The City Generator generates city names in US, UK, China or Japan.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regions	Select the region of the cities.
Languages	Select the language of the city names.

Region Generator

The Region Generator generates region names or ISO 3166 country codes in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Format	Generate region names, ISO 3166-1 alpha-2 or ISO 3166-1 alpha-3 country codes.
Languages	Select the language of the region names.

Product Name Generator

The Product Name Generator generates product names with the specified keywords.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Generate with keywords	Specify keywords for generating the product names.

Product Category Generator

The Product Category Generator generates product category names in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the category names.

Color Generator

The Color Generator generates color names in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the color names.

Size Generator

The Size Generator generates size (XS / S / M / L / XL) in English, Chinese or Japanese.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the size.

Weight Unit Generator

The Weight Unit Generator generates weight units from specified value list.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Values	Specify the weight units.

Barcode Generator

The Barcode Generator generates barcodes based on different barcode types or the specified format.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Types	Select the barcode types. You can customize Code39 barcode format in the Regular Expression box. For more information about regular expression, see Regular Expression Generator .

SKU Generator

The SKU Generator generates stock keeping units (SKU) based on the specified format.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

IP Address Generator

The IP Address Generator generates IPv4 or IPv6 addresses.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
IP Address Type	Generate IPv4 or IPv6 addresses.
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

MAC Address Generator

The MAC Address Generator generates random MAC addresses with the specified format.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

File Path Generator

The File Path Generator generates file paths for Windows, macOS or Linux.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Path type	Select the OS type of the file paths.

Include file name	Append file names to the end of the paths.
Extension Type	Choose the file extension type.
Extensions	Edit the file extensions.

File Name Generator

The File Name Generator generates file names.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Include extension	Append file extensions to the file names.
Extension Type	Choose the file extension type.
Extensions	Edit the file extensions.

File Extension Generator

The File Extension Generator generates file extensions.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Extension Type	Choose the file extension type.
Extensions	Edit the file extensions.

URL Generator

The URL Generator generates URLs with the specified subdomains and top-level domains.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Subdomain	Enter a list of website subdomains.
Top-Level-Domain	Enter a list of top-level domains.

Hostname Generator

The Hostname Generator generates server hostnames with the specified subdomains and top-level domains.

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Subdomain	Enter a list of website subdomains.
Top-Level-Domain	Enter a list of top-level domains.

Preview Data & Start Generation (Step 3)

You can preview the data that will be generated for each table.

Preview


Table:

customer_id	store_id	first_name	last_name	email	address_id	active	create_date
1	3	Ka Ling	Ti	klti@icloud.com	493	0	2014-02-13 08:19:05
2	2	Lu	Meng	lumeng@outlook.com	566	0	2018-02-27 20:25:31
3	1	Ayato	Kato	katoayat@outlook.com	191	0	2000-10-26 08:28:23
4	2	Ka Fai	Hsuan	kfh2@yahoo.com	310	1	2010-10-10 04:29:22
5	3	Jiehong	Gao	gajiehong@hotmail.com	536	1	2021-12-14 07:26:04
6	1	Edward	Thomas	thomasedward@gmail.com	511	1	2013-08-22 06:18:16
7	2	Anna	Cruz	cann922@gmail.com	73	1	2009-03-07 19:16:19
8	1	Chieh Lun	Fung	fchiehlun703@mail.com	540	0	2010-05-05 00:35:56
9	3	Chiu Wai	Chung	chung2@gmail.com	84	1	2017-09-12 14:22:24
10	1	Ka Ling	Tong	kalingtong304@outlook.com	63	1	2003-12-24 03:38:20
11	3	Ellen	Long	elllong@gmail.com	423	1	2006-05-25 13:43:43
12	2	Jialun	Lin	lin52@icloud.com	575	1	2003-03-18 03:43:22
13	1	Sau Man	Yau	yausm10@icloud.com	57	1	2012-10-15 02:39:28
14	3	Chi Yuen	Lok	cylo1210@gmail.com	243	0	2009-03-19 02:39:50
15	3	Lu	Dai	dailu@outlook.com	76	0	2017-10-09 08:43:02
16	1	Ikki	Sakai	is412@outlook.com	328	1	2012-03-13 07:07:15
17	3	Momoka	Matsuda	mamomoka@icloud.com	62	1	2016-08-24 12:17:11
18	1	Shihan	Wu	wu10@gmail.com	422	0	2012-11-20 06:59:01

Click the **Start** button to execute the data generation process. The window will display the execution progress, execution time, and success or failure messages.

Chapter 13 - Charts (Available only in Navicat Premium and Enterprise Edition)

About Charts

Charts feature allows you to create visual representations of your database data. In the main window, click  **Charts** to open the workspace object list.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB.

Some of key features are listed here:

- Support more than 20 chart types.
- Customize multiple pages dashboard.
- Visualize live data.
- Add interactive controls.

Hint: Workspace files (.ncharts) are saved under the [Profiles Location](#). To open the folder, right-click a workspace file and select **Open Containing Folder**. If the workspace is synchronized to [Navicat Cloud](#) or [On-Prem Server](#), it will be stored in the cloud.

Open an external workspace file

1. In the menu bar, choose **File -> Open External File -> Charts Workspace**.
2. Browse the file and click **Open** in the dialog window.

Save an opened external file as a Navicat workspace


1. In Workspace Designer, choose **File -> Save to Navicat**.
2. Enter the workspace name and choose the save location.
3. Click **OK**.

Save a Navicat workspace as an external file

1. In Workspace Designer, choose **File -> Save As External File**.
2. Choose the save path and enter the file name.
3. Click **Save**.

Workspace

A workspace is the place that comprises dashboards, charts and data sources. You can create multiple dashboards, charts and data sources in a workspace.



① Workspace Toolbar

The Workspace Toolbar provides controls that you can use to create data sources, charts and dashboards.

② Tab Bar

The Tab Bar allows you to switch among the opened items.

③ Content Pane

The Content pane shows all items in the workspace. To change the view, click the **Detail** or **Icon** button at the bottom of the window.


Detail View displays additional information about each item. You can sort items in Detail View, click the column header by which you want to sort the items.

Icon View displays your items as a grid of thumbnail images. You can filter the items by clicking a category (All, Data Source, Chart, Dashboard) in this view.

④ Properties Pane

The **General** tab shows the general information of the workspace or the selected item.

The **Using** tab shows the items that the selected item depends on.


The  **Used By** tab shows the items that depend on the selected item.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Data Source

About Data Source

Data sources reference tables in your connections and can select data from tables on different server types. The fields in the dataset can be used to construct a chart. When building a chart, you will need to specify the data source that the chart uses.



① Connections Pane

The Connections pane is the basic way to navigate with connections, databases, tables, queries.

② Data Source Toolbar

The Data Source Toolbar provides controls that you can use to manipulate the data.

③ Design Pane

The Design pane allows you to build the data source visually.

Navicat provides two modes for connecting your data: Live and Achieve.


Live mode retrieves data from your servers whenever the data source is being used / loaded. It offers the convenience of real-time updates, with any changes in the underlying data reflected.

Archive mode retrieves data from your servers during the data source creation, and stored the retrieved data in the workspace for later use by building charts.

④ Preview Pane

The Preview pane displays the data of the data source.

⑤ Properties Pane


The  **Properties** tab shows the general information of the data source. You can add a remark to the data source.

The  **Used By** tab shows the charts that depend on the data source.


If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.


Create Data Source

The essential steps to create a data source are:

1. In the Workspace window, click  **New Data Source**.
2. Enter the name of the data source and select the desired connections, files or existing data sources.

Option	Description
Database	Create data source using existing connections in Navicat, or create a new connection in the workspace. For more information about connection settings, see Connections .
File/ODBC	Import data to the workspace, or link the data source to the data in a supported external file or ODBC source. For more information about import steps, see Import Wizard .
Connections in Existing Data Sources	Choose the connections used in other existing data sources in the workspace.

3. Click **OK**.
4. A tab will open for you to edit the data source.
5. If you want to add more connections, click **+** and follow the steps.
6. Drag and drop tables from the Connections pane to the Design pane. You can view the table data by clicking .
7. Drag and drop a node to another to create the join.
8. Configure the join type and join fields if necessary.




Hint: After creating the join, you can change the join settings at any time by clicking the join icon on the connector.

9. Choose **Live** mode or **Archive** mode.
10. Click **Apply and Refresh Data** to view the data.



Add Query to Database Connection

For database connections, you can save query results to create a new dataset.

To create a new query

1. On the Connections pane, double-click  **New Data Source Query**.
2. Write the statement in [Query Editor](#). You can also use [Query Builder](#) to build the query visually.
3. Click **Save Query**.
4. Enter the name of the query and click **Save**.

To add an existing query

1. On the Connections pane, double-click  **New Data Source Query**.
2. Click  **Import Query**.
3. Select a query.
4. Click **Import**.
5. Click **Save Query**.
6. Enter the name of the query and click **Save**.

Modify Data Source Connections

My Connections

To change a connection in My Connections to a workspace connection

1. On the Connections pane, right-click a connection and select **Convert to Workspace Connection**.
2. The connection will be moved to the "Workspace" section.

To recreate a not found connection

If the server connection in My Connections was removed, it will be moved to the "Not Found in My Connections" section. You may need to recreate the connection in order to connect the server.

1. On the Connections pane, right-click a connection and select **Recreate Connection in My Connections**.
2. Enter the connection properties.
3. Click **OK**.

Project Connections

To change a project connection to a workspace connection

1. On the Connections pane, right-click a connection and select **Convert to Workspace Connection**.
2. The connection will be moved to the "Workspace" section.

To recreate a not found connection

If the server connection in the project was removed, it will be moved to the "Not Found in Project" section. You may need to recreate the connection in order to connect the server.

1. On the Connections pane, right-click a connection and select **Recreate Connection in Project**.
2. Enter the connection properties.
3. Click **OK**.

Workspace Connections

To edit the settings of a database connection

1. On the Connections pane, right-click a database connection and select **Edit Connection**.
2. Follow the steps to edit the connection.

To change the user password of a database connection

1. On the Connections pane, right-click a database connection and select **Change Connection Password**.
2. Enter the database user password.
3. Click **OK**.

To edit the settings of a file connection

1. On the Connections pane, right-click a file connection and select **Edit File Connection Settings**.
2. Follow the steps to edit the connection.


To change the path of a linked file connection



1. On the Connections pane, right-click a file connection and select **Change Linked File Path**.
2. Follow the steps to edit the connection.

Filter / Sort / Project Data

If your data source has many data or fields, you may find it easier to limit the data or fields to just the ones you want so you can simplify the data selections.

Filter Data

Filter pane allows you to facilitate creating and applying filter criteria that you specify for the data. Click  **Filter** from the toolbar to activate the Filter pane.

1. To add a new condition to the criteria, just simply click . If you want to add a condition with parentheses, click .
2. **Hint:** To add parentheses to existing conditions, simply right-click on the selected conditions and select **Group with Bracket**. To remove the parentheses, right-click a bracket and select **Delete Bracket** or **Delete Bracket and Conditions**.
3. Click on the field name (next to the checkbox) and choose a field from the list.
4. Click on the operator (next to the field name) and choose a filter operator.

Filter Operator	Operator Description
=	The field is equal to 'value'.
!=	The field is not equal to 'value'.
<	The field is less than 'value'.
<=	The field is less than or equal to 'value'.
>	The field is greater than 'value'.
>=	The field is greater than or equal to 'value'.
contains	The field contains 'value'.
does not contain	The field does not contain 'value'.


begin with	The field starts with 'value'.
does not begin with	The field does not start with 'value'.
end with	The field ends with 'value'.
does not end with	The field does not end with 'value'.
is null	The field is NULL.
is not null	The field is NOT NULL.
is empty	The field is empty.
is not empty	The field is not empty.
is between	The field is between 'value1' and 'value2'.
is not between	The field is not between 'value1' and 'value2'.
is in list	The field is in the list of ('value1','value2',...).
is not in list	The field is not in the list of ('value1','value2',...).

- Click on **<?>** to activate the appropriate editor and enter the criteria values. The editor used in the criteria values box is determined by the data type assigned to the corresponding field.
- Click on the logical operator (next to the criteria values) to choose **and** or **or**.
- Repeat step 1-5 to add another new condition.
- Click **Apply and Refresh Data** to see the result of the filtering you made.


Hint: If you want to reverse the meaning of the conditions, right-click the selected conditions and select **Toggle Negator**.


Sort Data

Navicat offers the ability to sort and order data. Click  **Sort** from the toolbar to activate the Sort pane.

- To add a new criteria, just simply click .
- Click on the field name (next to the checkbox) and choose a field from the list.
- Click on the sorting order to choose **ASC** or **DESC**.
- Repeat step 1-3 to add another new criteria.
- Click **Apply and Refresh Data** to see the result of the sorting you made.

Project Data

You can choose which fields to include or exclude in the data source. Click  **Projection** from the toolbar to activate the Projection pane.

- Choose to **Include** or **Exclude** fields.
- To add a new criteria, just simply click .

3. Click on the field name (next to the checkbox) and choose a field from the list.
4. Repeat step 2-3 to add another new criteria.
5. Click **Apply and Refresh Data** to see the result of the projection you made.


Add Custom Fields

You can extend your data with customized fields. New fields can be created by changing the field type, concatenating other fields, mapping to other values or sorting based on another field/customized order.

Create Custom Field


Type-Changed Field

Field types (String, Number, Date/Time) are assigned to every field based on the actual data type of the field. If the field was not interpreted correctly, you can adjust the field type.

1. In the bottom data grid, select a field and click  **New Custom Field -> Type-Changed Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. Choose the **Target Field Type**.
4. Set the **Source Field Data Format** if necessary.
5. Click **OK**.

Concatenated Field

You can add a new field and concatenate the data from two already existing fields.

1. In the bottom data grid, select a field and click  **New Custom Field -> Concatenated Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. Double-click a field on the **Source Fields** pane to add it to the body.
4. Edit the body and enable the **Set null if all field values are null or empty** option if necessary.
5. Click **OK**.

Mapped Field


You can create a new field populated with the results of applying a mapping rule on every value in the source field.

1. In the bottom data grid, select a field and click  **New Custom Field -> Mapped Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.

3. Click **Add** to create a new mapping rule.
4. Enable the **Compare source values with case sensitive** option if necessary.
5. Choose the action for the values that are not in the mapping rules.
6. Click **OK**.

Custom-Sorted Field

You can create a new field to rearrange the order of the values, based on another field, or a custom order. When you sort this new field in the chart, it will be sorted in the order you set.

1. In the bottom data grid, select a field and click  **New Custom Field -> Custom-Sorted Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. [Reference Field] Choose the field which the sort order of the target field will be based on.
4. [Custom] Customize the order of the field values by moving the values to the **Sorted Values** list.
5. Click **OK**.

Edit Custom Field

1. In the bottom data grid, right-click on the customized field and select **Edit XXX Field**.
2. In the pop-up window, modify the field properties.
3. Click **OK**.

Delete Custom Field


1. In the bottom data grid, right-click on the customized field and select **Remove XXX Field**.

Chart

About Chart

A chart provides visual representations of the data in your data source. It maps to a single data source, and can display correlations between several fields in the data. You can even make the chart interactive by adding a control chart.

Note: You must add a [data source](#) before you can begin building charts.



① Data Source Pane

The Data Source pane is the basic way to navigate with the data sources. If the Data Source pane is hidden, choose **View -> Show Data Source** from the menu bar.

② Chart Toolbar

The Chart Toolbar provides controls that you can use to manipulate the data.

③ Metric Pane

The Metric pane allows you to choose the chart type and add fields to the shelves from the Data Source Pane. If the Metric pane is hidden, choose **View -> Show Metric** from the menu bar.

④ Preview Pane

The Preview pane displays the chart.

⑤ Properties Pane

The **Properties** tab includes the basic layout settings, data format settings and so on. The properties vary with the type of the chart.


The **Using** tab shows the data sources that the chart depends on.

The **Used By** tab shows the dashboards that depend on the chart.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Build Chart

The essential steps to create a chart are:

1. In the Workspace window, click  **New Chart**.
2. Select the data source and enter the name of the chart.
3. A tab will open for you to edit the chart.
4. Choose the [Chart Type](#) on the middle pane.




Hint: The type of chart you will use is normally determined by the type of the data.

5. Drag fields to the corresponding shelf in the Metric pane to set axis, values, etc.
6. Select the properties on the right pane which can be further customized for your chart.

Hint: Each chart type has different properties.


7. The chart shows on the Preview pane.



Set Field Alias

You can create aliases for fields so that their labels appear differently in the chart.

1. Click the down arrow in the field box.
2. Select **Set Alias**.



3. Enter the alias name.

Filter / Sort Data


Filter Source Data in Chart

You can use the [Data Filter](#) pane to filter the source data in the current chart.


Filter Display Data in Chart

You can filter the display data in 3 ways:

- Click the down arrow in the field box and select **Display Filter**.



- Use the [Display Filter](#) pane.
- Right-click a series / data points on the chart.




Hint: If you want to clear the filter, you need to use the Display Filter pane.

Sort Data

You can sort the data in 2 ways:

- Click the down arrow in the field box and select **Sort**.




- Use the [Sort](#) pane.

Apply Aggregate Function

Aggregate functions allow you to summarize or change the granularity of your data.

1. Click the down arrow in the field box.



2. Select **Aggregate** and choose a aggregate function.


Function	Description
Number	
Sum	Return the sum of all values. Null values are ignored.
Average	Return the average of all the values. Null values are ignored.
Count	Return the number of items. Null values are not counted.
Count(Distinct)	Return the number of distinct items. Null values are not counted.
Min	Return the minimum value across all records. Null values are ignored.
Max	Return the maximum value across all records. Null values are ignored.
Median	Return the median value across all records. Null values are ignored.
DateTime	
Count	Return the number of items. Null values are not counted.
Count(Distinct)	Return the number of distinct items. Null values are not counted.
Year	Return the year of the date (0000-9999).
Quarter	Return the year of the date (0000-9999) and the quarter of the year (Q1-Q4).
Month	Return the year (0000-9999) and the month (01-12) of the date.
Week	Return the year of the date (0000-9999) and the week of the year (W01-W52, start of week is Sunday).

Day	Return the date.
Hour	Return the date and the hour of the time (00-23).
Minute	Return the date, the hour of the time (00-23) and the minute of the time (00-59).
Second	Return the datetime.
Quarter (Extract)	Return the quarter of the year (Q1-Q4).
Month (Extract)	Return the month of the date (01-12).
Week (Extract)	Return the week of the year (W01-W52, start of week is Sunday).
Day (Extract)	Return the day of the date (01-31).
Hour (Extract)	Return the hour of the time (00-23).
Minute (Extract)	Return the minute of the time (00-59).
Second (Extract)	Return the second of the time (00-59).
Text	
First	Return the value of the first record.
Last	Return the value of the last record.
Count	Return the number of items. Null values are not counted.
Count(Distinct)	Return the number of distinct items. Null values are not counted.

Add Range

You can aggregate data into ranges without the need to create any additional calculations in the data source.

1. Click the down arrow in the field box.



2. Select **Add Range**.
3. Edit the range settings.


Option	Description
Range Type - Fixed	
Bin Size	Either enter the size of a bin or click Calculate to let Navicat calculate a value for you.
Range Type - Custom	
Stop Values	Add the bin boundaries.

4. Click **OK**.

Set Value Operation

You can create a chart that shows a running total as values are added or subtracted.

1. Click the down arrow in the field box.



2. Select **Value Operation** and choose an operation.

Operation	Description
Cumulative	Sum the values cumulatively.
Subtract	Subtract the value with its previous value.

Chart Types

About Chart Types

Navicat provides a variety of different chart types so data can be displayed in a meaningful way.

Here is a complete list of available chart types:

- Vertical Bar Chart
- Vertical Stacked Bar Chart
- Horizontal Bar Chart
- Horizontal Stacked Bar Chart
- Line Chart
- Area Chart
- Stacked Area Chart
- Bar and Line Chart
- Stacked Bar and Line Chart
- Waterfall Chart
- Tornado Chart

- Pie Chart
- Donut Chart
- Scatter Chart
- Heatmap
- Treemap
- Value
- Trend
- KPI
- Gauge
- Table
- Pivot Table
- Control

Bar Chart

A bar chart provides high-level overviews of data trends by comparing values within a specific category.

- Vertical Bar Chart
- Vertical Stacked Bar Chart
- Horizontal Bar Chart
- Horizontal Stacked Bar Chart







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show Bar Labels	Display the data labels of the selected series.
Bar Label Contains	Display the data values or/and the percentages on the labels.
Bar Label Position	Set the position of the bar labels.
Use 100% stacked	Use 100% stacked bars to show values for hierarchical data. (Each bar height is 100%, and the colored bar segments represent the components' relative contributions to the total bar.)
Bar Label Font	Set the font style of the bar labels.
Use custom data value color	Customize the color of the labels of the data values.
Positive Data Value Color	Set the color of the positive value labels.
Negative Data Value Color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous data series on the chart.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
All Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.

Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Fill missing values	Use a continuous axis. The data series are positioned according to their domain value.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Show Y-Axis	Display Y-Axis line.
Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Trend Line	
	Add a trend line to the chart to show visual data trends.
	Remove the selected trend line.
	Rename the selected trend line.
Value	Select a data series for the trend line.
Group Value	Select a group value for the trend line.

Type	Choose the type of trend line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other trend lines	Align the trend line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Line / Area Chart

A line or area chart displays information as a series of data points connected by straight line segments.

- Line Chart
- Area Chart
- Stacked Area Chart







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.

Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Smoothed Line	Plot a smooth line through the data points.
Show Line Labels / Show Area Labels	Display the data labels of the selected series.
Line Label Contains	Display the data values or/and the percentages on the labels.
Line Label Pattern	Select the values that will be displayed on the chart.
Show markers	Display the marker points on the line / area.
Use 100% stacked	Use 100% stacked areas to show values for hierarchical data. (The area height is 100%, and the colored area segments represent the components' relative contributions to the total area.)
Use custom data value color	Customize the color of the labels of the data values.
Positive Data Value Color	Set the color of the positive value labels.
Negative Data Value Color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.

Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Fill missing values	Use a continuous axis. The data series are positioned according to their domain value.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Show Y-Axis	Display Y-Axis line.
Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Trend Line	
	Add a trend line to the chart to show visual data trends.
	Remove the selected trend line.
	Rename the selected trend line.
Value	Select a data series for the trend line.
Group Value	Select a group value for the trend line.
Type	Choose the type of trend line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other trend lines	Align the trend line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.

Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Bar and Line Chart

Mixing bar and line chart in the same visual is a good way to emphasize the difference between series while still maintaining their relationship.

- Bar and Line Chart
- Stacked Bar and Line Chart







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.

Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Smoothed Line	Plot a smooth line through the data points.
Show Labels	Display the data labels of the selected series.
Bar Label Contains	Display the data values or/and the percentages on the labels.
Bar Label Position	Set the position of the bar labels.
Bar Label Font	Set the font style of the bar labels.
Use 100% stacked bar	Use 100% stacked bars to show values for hierarchical data. (Each bar height is 100%, and the colored bar segments represent the components' relative contributions to the total bar.)
Line Label Contains	Display the data values or/and the percentages on the labels.
Line Label Pattern	Select the values that will be displayed on the chart.
Show line markers	Display the marker points on the line.
Use custom data value color	Customize the color of the labels of the data values.
Positive Data Value Color	Set the color of the positive value labels.
Negative Data Value Color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous data series on the chart.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
All Bar Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	

Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Fill missing values	Use a continuous axis. The data series are positioned according to their domain value.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis / Secondary Y-Axis	
Show Y-Axis title / Show Secondary Y-Axis title	Display the title of Y-Axis.
Y-Axis Title / Secondary Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis / Show Secondary Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels / Show Secondary Y-Axis labels	Display labels on Y-Axis.
Show Y-Axis / Show Secondary Y-Axis	Display Y-Axis line.
Y-Axis Color / Secondary Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Trend Line	
	Add a trend line to the chart to show visual data trends.
	Remove the selected trend line.
	Rename the selected trend line.
Value	Select a data series for the trend line.
Group Value	Select a group value for the trend line.
Type	Choose the type of trend line you want.

Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other trend lines	Align the trend line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Waterfall Chart

A waterfall chart is a special type of bar chart. It is useful for understanding how the starting value is affected by a series of changes (increase or decrease).




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.

Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show data values	Display the values of the data series.
Bar Label Position	Set the position of the bar labels.
Bar Label Font	Set the font style of the bar labels.
Total Bar Color	Set the color of the Total bar.
Subtotal Bar Color	Set the color of the Subtotal bar.
Total Bar Title	Specify the title of the Total bar.
Use increase and decrease color	Color the bars with Increase Color and Decrease Color.
Increase Color	Set the color of the bar when the value increases.
Decrease Color	Set the color of the bar when the value decreases.
Use custom data value color	Customize the color of the labels of the data values.
Positive data value color	Set the color of the positive value labels.
Negative data value color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous bars on the chart.
Density	Choose the density of the bars.
Group Value Sorting	Sort the group values (from Decrease to Increase, or from Increase to Decrease).
Color	Set the color palette of the data series.
All Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	

Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Fill missing values	Use a continuous axis. The data series are positioned according to their domain value.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Show Y-Axis	Display Y-Axis line.
Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.

Tornado Chart

A tornado chart is a special type of bar chart. It is useful for comparing data among different types of data or categories.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show Bar Labels	Display the data labels of the selected series.
Bar Label Contains	Display the data values or/and the percentages on the labels.
Bar Label Position	Set the position of the bar labels.
Bar Label Font	Set the font style of the bar labels.
Use stack	Use stacked bars to show values.
Use 100% stacked	Use 100% stacked bars to show values for hierarchical data. (Each bar height is 100%, and the colored bar segments represent the components' relative contributions to the total bar.)
Stacked Bar Style	Determine how the stacked section is displayed.
Negative Data Bar Background Color	Set the color of the negative data bars.
Minimum Value	Set the minimum value of the bar.
Data Label Color	Set the color of the data labels on the bars.
Use custom data value color	Customize the color of the labels of the data values.
Positive data value color	Set the color of the positive value labels.
Negative data value color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous bars on the chart.
Density	Choose the density of the bars.
Color	Set the color palette of the data series.

All Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Y-Axis	
Axis position	Set the position of Y-Axis.
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Fill missing values	Use a continuous axis. The data series are positioned according to their domain value.
Y-Axis Label Interval	Change the interval between Y-Axis labels.
Show Y-Axis labels	Display labels on Y-Axis.
Y-Axis Color	Set the color of Y-Axis line.
X-Axis	
Show X-Axis title	Display the title of X-Axis.
Left X-Axis Title	Specify the title of the left X-Axis.
Right X-Axis Title	Specify the title of the right X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Show grid line	Display the grid line of X-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on X-Axis.
Tick Interval	Set the interval of the tick marks in axis units.

Pie / Donut Chart

A pie or donut chart displays data in a series of segments of a circle, with larger segments representing larger data values.

- Pie Chart
- Donut Chart




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show data labels	Display data labels that clarify the data series.
Show data values	Display the values of the data series.

Show data percentages	Display the data percentages of the slices.
Show label inside slice	Position the slice labels inside the slice. Labels for smaller slices are hidden.
Show label over other slices	All labels are shown. Labels for smaller slices will overlap other slices.
Show slice separator	Add white borders between pie / donut slices.
Data Label Color	Set the color of the data label.
Show only top #	Only the top # data are displayed.
Slice	Group the small slices to a single slice (called Others).
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Group	
Show group title	Display the title of the group.
Group Title	Specify the title of the group.
Group Title Font	Set the font style of the group title.

Scatter Chart

A scatter chart plots data with individual data points placed along the X and Y axes.







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show size values	Display the size of the bubbles.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.

Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Show grid line	Display the grid line of X-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on X-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Show Y-Axis	Display Y-Axis line.
Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Trend Line	
	Add a trend line to the chart to show visual data trends.

	Remove the selected trend line.
	Rename the selected trend line.
Value	Select a data series for the trend line.
Group Value	Select a group value for the trend line.
Type	Choose the type of trend line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other trend lines	Align the trend line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Heatmap

A heatmap represents data in a tabular format as a range of color. A more intense color represents a larger aggregated value for a particular data point.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	

Background Color	Set the background color of the chart area.
Show Border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Label Color	Set the color of the legend labels.
Data	
Show data values	Display the values of the data series.
Data Label Color	Set the color of the data label.
Diverging	Use diverging color scale.
Use custom min/max values	Customize the color of the min, center, and max values. Navicat calculates the cell color based on the color of these values.
Min Color	Set the color of the minimum value in the colormap.
Center Color	Set the color of the value at which to center the colormap.
Max Color	Set the color of the maximum value in the colormap.
Min Value	Specify the minimum value.
Max Value	Specify the maximum value.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Column	
Show column title	Display the title of the column.
Column Title	Specify the title of the column.
Column Title Font	Set the font style of the column title.
Show column label	Display the column label.

Column Label Color	Set the color of the column label.
Row	
Show row title	Display the title of the row.
Row Title	Specify the title of the row.
Row Title Font	Set the font style of the row title.
Show row label	Display the row label.
Row Label Color	Set the color of the row label.

Treemap

A treemap is an alternative way of visualizing the hierarchical structure while also displaying quantities for each category via area size.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.

Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show data point names	Display the names of the data points.
Show data values	Display the values of the data points.
Show data percentages	Display the data percentages of the data points.
Data Label Color	Set the color of the data label.
Tile	Group the small tiles to a single tile (called Others).
Color	Set the color palette of the data points.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .

Value

A value displays a single aggregated value from a data field, e.g. total.

Total

\$259,619.25

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	

Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Data Label Font	Set the font style of the data label.
Negative Font Color	Set the color of the negative value.
Align	Set the horizontal alignment of the data label.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .

Trend

A trend displays that the current value is trending up or down compared to the previous value, and the percentage change.

514.18 ▼
2,523.01 -79.6%

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.

Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Show previous value	Display the previous value.
Show difference	Display the Value / Percentage difference between the current value and the previous value.
Show indicator	Display the up or down indicator.
Main Label Font	Set the font style of the main label.
Previous Value Color	Set the color of the previous value.
Target Met Color	Set the color of the indicator and the percentage when the value is trending up.
Target Missed Color	Set the color of the indicator and the percentage when the value is trending down.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.

KPI

A KPI displays a comparison between a key value and its target value with a progress bar.

4.20



Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Main Label Displayed	Display the Actual value or the Comparison percentage in the main label.
Main Label Font	Set the font style of the main label.
Indicator Thickness	Set the font size of the sub-label on the bar.
Sub Label Color	Set the color of the sub-label on the bar.
Target Caption	Specify the caption of the target label.
Use custom target value	Set the target value.
Target Label Color	Set the color of the target label.
Target Met Color	Set the color of the bar when the value reaches the target.
Target Missed Color	Set the color of the bar when value does not reach the target.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.

Gauge

A gauge is a meter type chart. It has a circular arc and displays a single value which measures the progress toward the target value (the goal).




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Show pointer	Display the needle.
Pipe Width Percentage	Set the percentage that the scale occupies the gauge area.
Background Color	Set the background color of the scale when the needle is not displayed.
Target Color	Set the color of the target line.
Pointer Color	Set the color of the needle.
Value Display	Display the actual data or the comparison percentage of the value.
Value Font	Set the font style of the value.
Target Display	Display the actual data or the comparison percentage of the target value.
Target Caption	Specify the caption of the target label.
Use custom target value	Set the target value.
Target Font	Set the font style of the target value.
Min/Max Displayed	Display the actual data or the comparison percentages of the minimum and maximum values.
Use custom min value	Set the value that the scale starts at.
Use custom max value	Set the value that the scale ends.
Min/Max Font	Set the font style of the minimum and maximum values.
Partition Label Displayed	Display the actual data or the comparison percentages of the partition

	labels.
Partition Label Font	Set the font style of the partition labels.
Partition (Max. 8)	Divide the scale into number of partitions.
Partition Style	Divide the scale equally or custom the starting percentage of each partition.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.

Table

A table represents data in a tabular view and calculates the total at the end of each column.

Job Title	No. of Employees
AC_ACCOUNT	31
AC_MGR	31
AD_ASST	31
AD_PRES	31
AD_VP	62
FI_ACCOUNT	155
FI_MGR	31
HR_REP	31
IT_PROG	155
MK_MAN	31
MK_REP	31
PR_REP	31
PU_CLERK	155
PU_MAN	31
SA_MAN	155
SA_REP	930
SH_CLERK	620
ST_CLERK	620
ST_MAN	155
	3317.00

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.

Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Font	Set the font style of the field names and data.
Show alternate row colors	Apply color to alternate rows.
Show vertical grid line	Display the vertical grid line.
Show horizontal grid line	Display the horizontal grid line.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Databar	
Style	Format the cells by using data bars.
Show bar only item	Only show the data bars in the cells, without the numbers.
Custom min/max values	Customize the min and max values of the data bars.
Min value	Specify the minimum value of the data bar.
Max value	Specify the maximum value of the data bar.
Positive bar color	Set the color of the data bars with positive values.
Negative bar color	Set the color of the data bars with negative values.
Axis color	Set the color of the axis for separating the positive bar and the negative bar.
Total	
Show total	Display totals in the last row of the table.
Total Color	Set the color of the total values.

Pivot Table

A pivot table shows measure values for the intersection of two dimensions and represents data in a tabular view.

Monthly State Sales Report

State	Apr	May	Jun	Jul	Aug	Sep	Oct	Total
BC	\$7,885		\$9,955					17840.00
CA						\$971.70		7259.55
Corfu								766.80
FL		\$2,814.70	\$0	\$32,793	\$10,712			46319.70
GA			\$0		\$18,532			18532.00
HI		\$3,115		\$8,524			\$64,050	91054.00
Jamaica		20,321.75		\$343.80		\$7,807	\$787.80	31070.20
OR		\$5,201	\$0			\$3,632		8833.00
Ontario		\$4,996						4996.00
St. Croix	\$0	\$6,500		\$25,210	\$1,238			32948.00
Total	7885.00	42948.45	9955.00	66870.80	30482.00	12410.70	64837.80	259619.25

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Font	Set the font style of the field names and data.
Show alternate row colors	Apply color to alternate rows.
Show vertical grid line	Display the vertical grid line.
Show horizontal grid line	Display the horizontal grid line.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Databar	

Style	Format the cells by using data bars.
Show bar only item	Only show the data bars in the cells, without the numbers.
Custom min/max values	Customize the min and max values of the data bars.
Min value	Specify the minimum value of the data bar.
Max value	Specify the maximum value of the data bar.
Positive bar color	Set the color of the data bars with positive values.
Negative bar color	Set the color of the data bars with negative values.
Axis color	Set the color of the axis for separating the positive bar and the negative bar.
Total	
Show row total	Display totals in the last row of the table. Enter the name of the row total, and set the color of the values and the background color.
Show column total	Display totals in the last column of the table. Enter the name of the column total, and set the color of the values and the background color.
Show row subtotal	Display totals in the last row of the group. Enter the name of the row subtotal, and set the color of the values and the background color.
Show column subtotal	Display totals in the last column of the group. Enter the name of the column subtotal, and set the color of the values and the background color.

Control

A control allows you to filter the data series of all charts in the dashboard that have the same data source during the presentation.

Month

- ☐ April
- ☐ May
- ☐ June
- ☐ July
- ☐ August
- ☐ September
- ☐ October
- ☐ November
- ☐ December
- ☐ November

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
--------	-------------

General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Data Label Color	Set the color of the data label.
Style	Show the data as a list, a range or a combo box.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .

DateTime Formats

The following table shows specifiers you can use to create user-defined data formats for DateTime fields in a chart.


Specifier	Description
D	Display the day as a number without a leading zero (1-31).
DD	Display the day as a number with a leading zero (01-31).
M	Display the month as a number without a leading zero (1-12).
MM	Display the month as a number with a leading zero (01-12).
MMM	Display the month as an abbreviation (Jan-Dec).
MMMM	Display the month as a full month name (January-December).
MMMMM	Display the month as a narrow name (J-D).
YY	Display the year in two-digit numeric format with a leading zero (00-99).
YYYY	Display the year in four-digit numeric format (0000-9999).
h	Display the hour as a number without a leading zero using the 12-hour

	clock (1-12).
hh	Display the hour as a number with a leading zero using the 12-hour clock (01-12).
H	Display the hour as a number without a leading zero using the 24-hour clock (0-23).
HH	Display the hour as a number with a leading zero using the 24-hour clock (00-23).
m	Display the minute as a number without a leading zero (0-59).
mm	Display the minute as a number with a leading zero (00-59).
S	Display the second as a number without a leading zero (0-59).
SS	Display the second as a number with a leading zero (00-59).
wd	Display the day as a single letter abbreviation (S-S).
Wd	Display the day as an abbreviation (Sun-Sat).
WD	Display the day as a full name (Sunday-Saturday).
w	Display the week of the year (1-52, start of week is Sunday).
WW	Display the week of the year (W01-W52, start of week is Sunday).
q	Display the quarter of the year (1-4).
QQ	Display the quarter of the year (Q1-Q4).
p	Display an uppercase AM with any hour before noon; display an uppercase PM with any hour between noon and 11:59 P.M.

Dashboard

About Dashboard

Dashboard is a collection of charts which allows you to create and view your data visualizations. When you modify a chart, any dashboards containing it will reflect the changes.



① Pages Pane

The Pages pane shows thumbnail images of each page in the dashboard. If the Pages pane is hidden, choose **View -> Show Pages** from the menu bar.


② Dashboard Toolbar

The Dashboard Toolbar provides controls that you can use to refresh the data and present the dashboard.

③ Design Pane

You can design your dashboard on the Design pane. All added objects can be moved (by dragging them with mouse or by keyboard), resized, aligned to the grid, etc.

④ Properties Pane


The  **Dashboard Properties** tab includes the basic layout settings. The properties vary with the type of the object.

The  **Using** tab shows the charts and data sources that the dashboard depends on.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Build Dashboard

The essential steps to create a dashboard are:

1. In the Workspace window, click  **New Dashboard**.
2. Enter the name of the dashboard.
3. Click **OK**.
4. A tab will be opened for your newly created dashboard.
5. Design your dashboard.
6. Select the properties on the right pane which can be further customized for your dashboard.

Note: Each object has different properties.

Hint: You can refresh dashboard to update data in charts with the most current data from their respective data sources.

To manually refresh the dashboard, click  **Refresh Data**.

Working with Grids

Show Grid

To turn the grid on in the dashboard, choose **View -> Show Grid** from the menu bar.

Snap to Grid

To align objects on the dashboard with the grid, choose **View -> Snap to Grid** from the menu bar.

Add Pages

The Pages pane shows all pages in the dashboard. It displays thumbnails of your dashboard pages.

To add a new page

1. On the Dashboard tab, click the **+** button on the Pages pane.
2. A blank page will be added and selected.

Properties



The available properties of a page:

Option	Description
General	
Dashboard Page Size	Customize the size of pages in the dashboard.
Remarks	Enter remarks for the dashboard.
Page #	
Background	Set the background color of the page. If you choose Image Fill , you can choose the image file and the scaling option.
Opacity	Set the opacity of the image.
Page Note	Enter the reference, comment, or explanation of the page.

Add Charts

Charts provide visual representations of the data in your data source.

To add a chart

1. On the Dashboard tab, click  **Add Chart**.
2. All available charts in the workspace will be shown as thumbnails. If no charts are available, click  **New Chart** to create one. For detailed instructions on creating charts, see [Build Charts](#).
3. Drag a chart to the Design pane.

Properties


The available properties of a chart:

Option	Description
Position	Customize the position of the chart.
Size	Customize the size of the chart.

Add Text Labels

Text labels are typically used to help document the dashboard, such as adding a dashboard title, URL links.

To add a text label

1. On the Dashboard tab, click  **Add Text**.
2. Place it on the dashboard.
3. Enter the caption.

Properties


The available properties of a text label:

Option	Description
Position	Customize the position of the label.
Size	Customize the size of the label.
Caption	Enter the caption of the label.
Horizontal Alignment / Vertical Alignment	Specify the text alignment of the label caption.
Padding	Set the horizontal and vertical padding for the text.
Font	Set the font style of the label caption.
Bold	Apply a bold style to the label caption.
Italic	Apply an italic style to the label caption.
Background Color	Set the background color of the label.
Opacity	Set the opacity of the background color.
URL	Enter URL path to set the text as a hyperlink.

Add Images

You can insert images (BMP, JPG, JPEG or PNG files) to your dashboard for design or identification purposes.

To add an image

1. On the Dashboard tab, click  **Add Image**.
2. Select an image file in the Open dialog box.

Properties

The available properties of an image:


Option	Description
Opacity	Set the opacity of the image.
Position	Customize the position of the image.

Size	Customize the size of the image.
Original Size	Reset the image to its original size.
URL	Enter URL path to set the image as a hyperlink.

Add Shapes

Navicat includes some pre-defined shapes for creating a dashboard: line, arrow, rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man, woman.

To add a shape

1. On the Dashboard tab, click  **Add Shape** and choose a shape type.
2. Place it on the dashboard.

To add a vertex on a line or an arrow

1. Select a line or an arrow on the dashboard.
2. Press and hold the SHIFT key and click on it.

To delete a vertex on a line or an arrow

1. Select a line or an arrow on the dashboard.
2. Press and hold the SHIFT key and click on the vertex.

Properties

The available properties of a shape:

Option	Description
Position	Customize the position of the shape.
Size	Customize the size of the shape. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Color	Set the color of the shape.
Show border	Display the outer shape border. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Border Color	Change the color of the shape's border. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Border Width	Choose the thickness of the border. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.

Line Width	Choose the thickness of the shape.
Cap Style	Choose the cap style of the line/arrow.
Dash Style	Choose the dash style of the line/arrow.
Join Style	Choose the join style of the line/arrow.
Begin Arrow Style	Choose the style of the arrow's back.
End Arrow Style	Choose the style of the arrow's front.

Arrange Objects

You can arrange the objects on a dashboard page in the following ways:

- Move objects forward and backward to layer them.
- Align an object with other objects.
- Distribute the objects horizontally or vertically.
- Group objects to more easily move them as a single unit and synchronize the axis of the related charts.
- Lock objects to prevent them from moving, modifying, or deleting.

Move Objects Forward / Backward

To send an object to the back of the dashboard, right-click it and select **Send to Back**.

To bring an object to the front of the dashboard, right-click it and select **Bring to Front**.

Align Objects

Select multiple objects, then right-click and select **Alignment** -> **Align Left**, **Align Center**, **Align Right**, **Align Top**, **Align Middle** or **Align Bottom**.

Change Objects Distribution

Select multiple objects, then right-click and select **Distribute** -> **Horizontal** or **Vertical**.

Group Objects

Select multiple objects, then click **Group** on the Properties pane and enable the following properties if necessary.

Option	Description
Link Scrolling	Synchronize the scrollbar of all charts.
Link Highlight	Hover over a data point on one of the charts will highlight the same data points on the others.
Show Hints When Highlight	Pop up the hint labels when hovering over a data point on one of the charts.

Ungroup Objects

Select the group, then click **Ungroup** on the Properties pane.


Lock Objects

Select an object, then click **Lock** on the Properties pane.

Unlock Objects

Select the locked object, then click **Unlock** on the Properties pane.

Present Dashboard



You can present the dashboard using the whole screen. The title bar, toolbar, tab bar, Pages pane, Control List and Properties pane will be hidden while in this mode. To open a dashboard in present view, click  **Present**.

If you have added a [control](#) chart to your dashboard, you can filter the data series of all charts by using the control.

To exit present view, press the ESC key and the workspace window will be returned to its previous state.

Sort Chart

In the Present mode, you can organize your data in a chart with one click. You can sort data series by a value.

1. Hover over a chart until you see the  icon in the upper-right corner.
2. Click the  icon to sort on a different value and select the sorting order.

Print & Export Dashboard


Print to a printer


Choose **File -> Print** to send your dashboard pages directly to the printer. You can set the printer option in the pop-up window.

Export to a file

Choose **File -> Export To** and choose the file format to create a PDF, PNG, SVG or JPG file of your dashboard pages.


Switch Theme

Charts are not affected by the software theme selected in [Options](#). If you want use a Dark theme for your charts, click  **Switch Theme** to change the theme.



Chapter 14 - Automation (Available only in Non-Essentials Edition)

About Automation

Navicat allows you to automate executing jobs at one or more regular intervals, beginning and ending at a specific date and time using **Windows Task Scheduler**. Automation can be created for Query, Backup, Data Transfer, Data Synchronization, Data Generation, Charts, Import, Export, MongoDB, MongoDBImport, MongoDBExport, MapReduce. You can define a list of jobs to be performed within one batch job, either run it manually, at the specified time or periodically. In the main window, click  **Automation** to open the automation object list.

Hint: Batch Job files are saved under the [Profiles Location](#).

Hint: You can run a batch job in Windows Command Prompt with this command:


```
navicat.exe -batchjob BatchJobName
```

Example: `navicat.exe -batchjob job1`


Create Batch Job (Step 1)

Add Jobs to Batch Job

In the bottom pane of the **General** tab, select the job type, and then browse the connection, database and/or schema to locate jobs if necessary.





Move jobs from the **Available Jobs** list to the **Selected Jobs** list by double-clicking or dragging them. To delete the jobs from the Selected Jobs list, remove them in the same way. You are allowed to run profiles from different servers in a single batch job.

To rearrange the sequence of the selected jobs, use the  **Move Up** or  **Move Down** buttons.

If you want to backup whole server, you can select the connection and select **Backup Server xxx**.

You can export dashboards to PDF files. Adding a Charts workspace file to the Selected Jobs list will allow you to choose the export file format and specify the target directory. You can enable the **Append timestamp to file name** option to append timestamp to the name of the exported file.

Exported files can be added to the batch job as mail attachment. Select the job in the Selected Jobs list and click  **Attach to Email** or  **Detach from Email** to add or remove the mail attachment.

Set Advanced Options & Email Notification

Continue on error

Ignore errors that are encountered during the job execution process.

Send Email

Navicat allows you to generate and send personalized emails with results returned from a schedule. The results can be emailed to multiple recipients.

When

Specify when to send notification emails: the task completed successfully and/or failed.

From

Specify email address of sender. For example, someone@navicat.com.

To, CC

Specify email addresses of each recipient, separating them with a comma or a semicolon (;).

Subject

Specify the email subject with customized format.

Body

Write email content.

Host (SMTP Server)

Enter your Simple Mail Transfer Protocol (SMTP) server for outgoing messages.

Port

Enter the port number you connect to your outgoing email (SMTP) server.

Use authentication

Check this option and enter **User Name** and **Password** if your SMTP server requires authorization to send email.

Secure connection


Specify the connection to use **TLS**, **SSL** secure connection or **Never**.

Send Test Mail



Navicat will send you a test mail indicating success or failure.


Save / Run Batch Job

Before setting schedule, click the  **Save** button to save the batch job.


You can run the batch job manually by clicking the  **Start** button. The **Message Log** tab displays the execution progress, execution time, and success or failure messages.

Schedule Batch Job (Step 2)

You can click  **Set Task Schedule** to set schedule for running a batch job and click  **Delete Task Schedule** to remove the schedule.




If you choose **Run whether user is logged on or not** in the **General** tab, then you must provide your OS user password in Windows Scheduler when you save the schedule.



A dialog box titled "Enter Account Information for Task Registration" with a blue header bar containing a key icon. The main area is light gray and contains the text "Account information for task registration:". Below this, there are two input fields: "User name:" with a dropdown menu showing "admin" and a small "..." button to its right, and "Password:" with a text box filled with ten black dots. At the bottom right, there are two buttons: "OK" and "Cancel".

Note: Please save the batch job before setting schedule. Passwords must be saved in the [Connection](#) window before running your schedule.



A form with a light gray background. It contains four labels on the left: "Host:", "Port:", "User Name:", and "Password:". To the right of each label is an input field. The "Host:" field contains "localhost". The "Port:" field contains "3380". The "User Name:" field contains "root". The "Password:" field contains ten black dots. Below the "Password:" field is a checkbox with a blue checkmark and the text "Save password".

Chapter 15 - Backup & Restore

About Backup & Restore


A secure and reliable server is closely related to performing regular backups, as failures will probably occur sometimes - caused by attacks, hardware failure, human error, power outages, etc.

Navicat provides backup and restore tools for users to backup/restore database objects.

- [Built-in backup and restore tool](#) for MySQL / PostgreSQL / SQLite / MariaDB
- [Oracle Data Pump](#)
- [SQL Server Backup & Restore](#)
- [MongoDump & MongoRestore](#)
- [Built-in backup and restore tool](#) for Redis

MySQL / PostgreSQL / SQLite / MariaDB (Available only in Non-Essentials Edition)

About Built-in Backup & Restore Tool

The built-in backup & restore tool allows you to backup/restore database objects for your database. You can save your settings as a profile for future use or setting [automation tasks](#). In the main window, click  **Backup** to open the backup object list.

Hint: Backup files are saved under the [Settings Location](#). To open the folder, right-click a backup file and select **Open Containing Folder**.

Note: Available only for MySQL, PostgreSQL, SQLite and MariaDB.

Backup

General Properties

In this tab, you can view the server and database information. Enter a comment for the backup file if necessary.

Object Selection

In this tab, choose database objects you wish to backup.

All <objects> during execution (*)	All the database objects being backed up, all newly added database objects will also be backed up without amending the backup profile.
Custom	Only the checked database objects will be backed up. However, if

	you add any new database objects in the database and/or schema after you create your backup profile, the newly added database objects will not be backed up unless you manually modify the Objects list.
--	--

Advanced Properties

Note: The following options depend on the connection server type and sort in ascending order.

Lock All Tables

Lock all objects while backup is being processed.

Use Single Transaction (InnoDB only)

If a table uses InnoDB storage engine, with this option is on, Navicat uses transaction before the backup process starts.

Use specified file name

Define your file name for backup. Otherwise, your backup file will be named with "YYYYMMDDhhmmss" format.

Restore

Restore feature will firstly drop the selected objects of the database, then recreate the new objects according to your backup. Finally, inserting the data.

Restore a backup to an existing database/schema

1. In the main window, open a database/schema.
2. Click **Backup** and select an existing backup file.
3. Click **Restore Backup** from the object toolbar.
4. Choose the restore options and click **Restore**.

Restore a backup to a new database/schema

1. Create and open a new database/schema.
2. Click **Backup**.
3. In the Objects tab, right-click anywhere and select **Restore Backup from**.
4. Browse the backup file.
5. Choose the restore options and click **Restore**.

Hint: You can also restore Navicat macOS and Linux backups.

Note: You must have Create, Drop and Insert privileges ([MySQL/MariaDB](#) or [PostgreSQL](#)) to run the restore.

General Properties

In this tab, you can view the target server and database information and the backup file information.

Object Selection

In this tab, choose database objects you wish to restore.

Advanced Properties

Note: The following options depend on the connection server type, the backup file version and sort in ascending order.

Continue on error

Ignore errors that are encountered during the restore process.

Create indexes

Create indexes for the restored table with this option is on.

Create tables

Create tables during the restore process with this option is on.

Create records

Restore table records with this option is on. Otherwise, only table structures will be restored.

Create triggers

Create triggers for the restored table with this option is on.

Empty table

Delete all table records in the database/schema.

Lock tables for write

Lock the tables to prevent user to modify tables during the restore process.

Insert auto increment values

Insert auto increment values in the database/schema.

Overwrite existing events

Overwrite if events already exist in the database/schema.

Overwrite existing functions

Overwrite if functions already exist in the database/schema.

Overwrite existing indexes

Overwrite if indexes already exist in the database/schema.

Overwrite existing sequences

Overwrite if sequences already exist in the database/schema.

Overwrite existing tables

Overwrite if tables already exist in the database/schema.

Overwrite existing triggers

Overwrite if triggers already exist in the database/schema.

Overwrite existing types

Overwrite if types already exist in the database/schema.

Overwrite existing views

Overwrite if views already exist in the database/schema.

Run multiple queries in each execution

Check this option if you want to run multiple queries in each execution, which will make the restore process faster.

Use extended insert statements

Check this option if you want to insert records using extended insert syntax.

Example: *INSERT INTO `users` VALUES ('1', 'Peter McKindy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');*

Use transaction

Check this option if you want to rollback all data when error occurs.

Extract SQL

Extract SQL allows extracting SQL into a SQL file from your backup file.

Extract a backup file that is in your database/schema

1. Open a database/schema.
2. Click **Backup** and select an existing backup file.
3. Click **Extract SQL** from the object toolbar.


4. Choose the [Extract SQL options](#) and click **Extract**.
5. Choose a path for the SQL file.

Extract a backup file that is in any location

1. Open any one of your databases/schemas.
2. Click **Backup**.
3. In the Objects tab, right-click anywhere and select **Extract SQL from**.
4. Click **Extract SQL** from the object toolbar.
5. Browse the backup file.
6. Choose the [Extract SQL options](#) and click **Extract**.
7. Choose a path for the SQL file.

Oracle Data Pump (Available only in Non-Essentials Edition)

About Oracle Data Pump

Data Pump includes two utilities: Data Pump Export and Data Pump Import. Data Pump Export is for unloading data and metadata into a dump file set. Data Pump Import is for loading an export dump file set into a target system. In the main window, click  **Data Pump** to open the data dump object list.

To change the directory of the dump file set, right-click anywhere in the Objects tab and select **Change Directory**.

Note: Data Pump is added in Oracle 10g or later. You require SYSDBA role to perform it. Dump file sets are stored in servers.

Oracle Data Pump Export

Before executing Data Pump Export, click the **Generate SQL** button to review the SQL statements. Then, you can click the **Execute** button to run the export process.

You can save the Data Pump Export settings to a profile for future use. Data Pump Export profiles (.nbakora) are saved under the [Settings Location](#).

To show the hidden tabs (advanced options), check the **Show Advanced Options** option.

General Properties

Job Name

Specify the name of the job.

Mode

Choose the export mode: FULL, TABLESPACE, SCHEMAS, TABLE.

Content

Choose which data to export.

Export Data

Select which objects to export. If you select the TABLE export mode, choose a schema in the **Export Schema(Table Mode)** drop-down list.

Dump Files

Add dump files to the dump file set for the export.

Metadata Filter

In this tab, you can include or exclude specific objects types.

Data Filter

Query

Specify a subquery that is added to the end of the SELECT statement for a table.

Sample

Specify a percentage for sampling the data blocks to be moved.

Remap Data

In this tab, you can specify remap functions for column data.

Encryption

Encryption Content

Choose what to encrypt in the dump file set.

Encryption Algorithm

Choose a cryptographic algorithm to perform encryption.

Encryption Mode

Choose the encryption mode: Transparent, Encryption Password, Dual.

Encryption Password

If you choose the Encryption Password or Dual encryption mode, enter a password to encrypt data written to the dump file.

Confirm Password

Re-type your password.

Advanced Properties

Thread Number

Enter the maximum number of worker processes that can be used for the job.

Reuse File

Check this option to overwrite a preexisting file.

Enable XMLCLOBS

Check this option to enable data options for XMLCLOBS.

Enable Cluster

Check this option to start workers on instances usable by the job.

Service Name

Specify a service name that used to constrain the job to specific instances or to a specific resource group.

Source Edition

Specify the application edition.

Version

Specify the version of database objects to be extracted.

Compression Type

Specify which data to compress before writing to the dump file set.

Transportable

If you select the TABLE export mode, choose to never or always use the transportable option.

Database Link

Choose a database link to the remote database that will be the source of data and metadata for the job.

Estimate

Choose the estimate method for the size of the tables should be performed before starting the job.

Access Method

Choose an alternative method to unload data if the default method does not work.

Log File Directory

Choose the directory for saving the log file.

Log File Name

Enter the name of the log file.

Flashback SCN

Enter the system change number (SCN) that used to enable the Flashback Query utility.

Flashback Time

Select a timestamp for finding a SCN.

Oracle Data Pump Import

Before executing Data Pump Import, click the **Generate SQL** button to review the SQL statements. Then, you can click the **Execute** button to run the import process.

To show the hidden tabs (advanced options), check the **Show Advanced Options** option.

General Properties

Job Name

Specify the name of the job.

Mode

Choose the import mode: FULL, TABLESPACE, SCHEMAS, TABLE.

Content

Choose which data to import.

Table Exists Action

Specify the action to be performed when data are loaded into a preexisting table.

Import Data

Select which objects to import. If you select the TABLE import mode, specify the schema name in the **Schema** text box.

Dump Files

Add dump files to the dump file set for the import.

Network

Database Link

Choose a database link to the remote database that will be the source of data and metadata for the job.

Estimate

Choose the estimate method for the size of the tables should be performed before starting the job.

Flashback SCN

Enter the system change number (SCN) that used to enable the Flashback Query utility.

Flashback Time

Select a timestamp for finding a SCN.

Transportable

If you select the TABLE export mode, choose to never or always use the transportable option.

DataFile Path

Specify the full file specification for a datafile in the transportable tablespace set.

Filter

Include/Exclude

Include or exclude specific objects types.

Query

Specify a subquery that is added to the end of the SELECT statement for a table.

Remap Data

Remap Data

Specify remap functions for column data.

Remap DataFiles

Specify the remapping for data files.

Remap Objects

Remap Schemas

Specify the remapping for schemas.

Remap TableSpaces

Specify the remapping for tablespaces.

Remap Tables

Specify remap functions for tables.

Advanced Properties

Thread Number

Enter the maximum number of worker processes that can be used for the job.

Reuse datafiles

Check this option to reuse existing data files for creating tablespace.

Skip unusable indexes

Check this option to skip loading tables that have indexes that were set to the Index Unusable state.

Streams configuration

Check this option to import any general Streams metadata that may be present in the export dump file.

Skip const error

Check this option to skip constraint violations and continue the load.

Disable append hint

Check this option to prevent the append hint from being applied to the data load.

Cluster

Check this option to start workers on instances usable by the job.

Service Name

Specify a service name that used to constrain the job to specific instances or to a specific resource group.

Target Edition

Specify the database edition into which objects should be imported.

Version

Specify the version of database objects to be extracted.

Access Method

Choose an alternative method to unload data if the default method does not work.

Partition Options

Choose how to handle partitioned tables during the import operation.

Encryption Password

Enter the password if an encryption password was specified in Data Pump Export.

Segment Attributes, Segment Creation, Storage, OID, PCTSpace

Choose the objects that the transformations to be applied to.

Log File Directory


Choose the directory for saving the log file.

Log File Name

Enter the name of the log file.

SQL Server Backup & Restore (Available only in Non-Essentials Edition)

About SQL Server Backup & Restore

The **SQL Server Backup** feature provides an important safeguard for protecting your SQL Server data. In the main window, click  **SQL Server Backup** to open the backup object list.

If you want to backup with the setting of an existing backup file, you can right-click a backup file in the Objects tab and select **Backup From This Setting**.

Note: Backup files are stored in servers.

If you want to restore from a backup file that is not listed in the Objects tab, you can right-click anywhere in the Object pane and select **Restore From File**.

SQL Server Backup

Before starting the backup process, click the **Generate SQL** button to review the SQL statements. Then, you can click the **Backup** button to run the backup process.

You can save the backup settings to a profile for future use. Backup profiles (.nbakmssql) are saved under the [Settings Location](#).

To show the hidden tabs (advanced options), check the **Show Advanced Options** option.

General Properties

Backup Set Name

Specify the name of the backup set.

Description

Specify the description of the backup set.

Backup Type

Choose the type of the backup that you want to perform: Full Backup, Differential Backup, Transaction-Log Backup.

Copy-only

Check this option to specify that the backup is a copy-only backup.

New Media Set

Create a new media set for this backup. To add backup devices or files to the list, click the **Add device** button.

Existing Media Set

Choose an existing media set for the backup.

Components

In this tab, you can choose to backup the whole database, the partial database, or specific files or groups.

Advanced Properties

Never expire

Specify the backup set never expires.

Expire after

Specify the number of days that must elapse before this backup media set can be overwritten.

Expire on

Specify when the backup set expires and can be overwritten.

Password

Enter a password for the backup set.

Format media set

Check this option to specify that a new media set be created.

New Name

Enter the name of the new media set.

Description

Specify the description of the media set.

Overwrite all backups

Check this option to specify that all backup sets should be overwritten, but preserves the media header.

Check media name and backup set expiration

Check this option to check the expiration date and time of the backup sets on the media before overwriting them.

Media Set Name

Specify the media name for the entire backup media set.

Password

Enter a password for the media set.

Truncate the transaction log

Choose this option to truncate the transaction log.

Backup the tail log and set database to recovery state

Choose this option to back up the tail of the log and leaves the database in the RESTORING state.

Verify backup

Check this option to verify the backup.

Perform checksum

Check this option to enable the backup checksums.

Continue on error

Ignore errors (such as invalid checksums or torn pages) that are encountered during this backup.

Compression

Choose whether backup compression is performed on this backup.

SQL Server Restore

Before starting the restore process, click the **Generate SQL** button to review the SQL statements. Then, you can click the **Restore** button to run the restore process.

General Properties

Restore to database

Select a database to restore.

Source of backup set

If you chose **Restore From File** in the Objects tab, you can add backup devices or files to the list by clicking the **Add device** button.

Latest possible

Choose this option if do not have the restore point.

Specific time

Choose this option to specify that the database be restored to the state it was in as of the date and time.

Marked transaction

Choose this option to recover to a specified recovery point.

Include marked transaction

Check this option to include the specified transaction in the recovery.

Restore plan

If you chose **Restore From File** in the Objects tab, you can choose the database backup files from the list.

Advanced Properties

Restore database files to

Specify that the data or log file should be moved by restoring it to the **Restore To** location.

WITH REPLACE

Check this option to include the WITH REPLACE argument.

WITH RESTRICTED_USER

Check this option to include the WITH RESTRICTED_USER argument.

WITH KEEP_REPLICATION

Check this option to include the WITH KEEP_REPLICATION argument.

RECOVERY

Choose this option to roll back all uncommitted transactions.

NORECOVERY

Choose this option to not roll back the uncommitted transactions.

STANDBY

Specify a **Standby file** that allows the recovery effects to be undone.

MongoDump & MongoRestore

About MongoDump & MongoRestore

MongoDB provides two utilities for backup and restore operations: MongoDump and MongoRestore. They are useful for creating backups of small database and restoring data.

MongoDump

MongoDump can read data from a MongoDB database and create high fidelity BSON files.

Note: You must have [mongodump](#) executable for this feature to work.

To dump a file

1. In Navicat main window, right-click your database or collection and select **MongoDump**.
2. In the **General** and **Advanced** tabs, select the output path and the appropriate dump options.
3. Click the **Start** button to begin the dump process. The **Message Log** tab will display the dump progress, execution time, and success or failure messages.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the [Profiles Location](#).

MongoRestore

MongoRestore can load data from a binary database dump created by MongoDump into a MongoDB database.

Note: You must have [mongorestore](#) executable for this feature to work.

To restore database


1. In Navicat main window, right-click your database and select **MongoRestore**.
2. In the **General** and **Advanced** tabs, select the input file/directory path and the appropriate restore options.
3. Click the **Start** button to begin the restore process. The **Message Log** tab will display the restore progress, execution time, and success or failure messages.

You can save your settings as a profile for future use. To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the [Profiles Location](#).

Redis (Available only in Non-Essentials Edition)

About Built-in Backup & Restore Tool

The built-in backup & restore tool allows you to backup/restore database objects for your database. You can save your settings as a profile for future use or setting [automation tasks](#). In the main window, click  **Backup** to open the backup object list.

Hint: Backup files are saved under the [Settings Location](#). To open the folder, right-click a backup file and select **Open Containing Folder**.

Note: Available only for Redis.

Backup

General Properties

In this tab, you can view the server and database information. Enter a comment for the backup file if necessary.

Options

Key Pattern

Enter a key pattern. Navicat only backs up keys that match the specified pattern.

Data Types

Choose the type of data to back up.

Include volatile keys

Include keys with timeout expiration set.

Store TTL information

Back up the Time-to-Live (TTL) information of volatile keys.

Use specified file name

Define your file name for backup. Otherwise, your backup file will be named with "yyyymmddhhmmss" format.

Restore

Restore feature will firstly delete the keys in the selected namespaces, then recreate the keys.

Restore a backup to an existing database

1. In the main window, open a database.
2. Click **Backup** and select an existing backup file.
3. Click **Restore Backup** from the object toolbar.
4. Choose the restore options and click **Restore**.

Restore a backup to another database

1. Open another database.
2. Click **Backup**.
3. In the Objects tab, right-click anywhere and select **Restore Backup from**.
4. Browse the backup file.
5. Choose the restore options and click **Restore**.

Hint: You can also restore Navicat macOS and Linux backups.

General Properties

In this tab, you can view the target server and database information and the backup file information.

Details

In this tab, you can view the backup settings and summary.

Namespace Selection

In this tab, choose namespaces you wish to restore.

Advanced Properties

Data Types

Choose the type of data to restore.

Include persistent keys

Include keys that will never expire.

Include volatile keys

Include keys with timeout expiration set.

Include TTL information

Restore the Time-to-Live (TTL) information of volatile keys. You can choose to restore the remaining TTL, the original expiration time or a custom TTL.

Delete key before restoring if key exists

If keys already exist in the target database, the existing keys will be deleted once the restore process starts.

Delete all keys of the target database before restoring

Delete all keys in the target database once the restore process starts.

Delete asynchronously

Delete keys from the server asynchronously. The operation will be executed in a background thread.

Disable replies from server

Stop the server from replying to commands.

Continue on error

Ignore errors that are encountered during the restore process.

Extract Command

Extract Command allows extracting commands into a Redis command file from your backup file.

Extract a backup file that is in your database



1. Open a database.
2. Click **Backup** and select an existing backup file.
3. Click **Extract Command** from the object toolbar.
4. Choose the [Extract Command options](#) and click **Extract**.
5. Choose a path for the command file.

Extract a backup file that is in any location

1. Open any one of your databases.
2. Click **Backup**.
3. In the Objects tab, right-click anywhere and select **Extract Command from**.
4. Browse the backup file.
5. Choose the [Extract Command options](#) and click **Extract**.
6. Choose a path for the command file.

Chapter 16 - Server Security

About Server Security

Navicat provides a powerful tool for you to manage server user accounts and the privileges of database objects. All information of users and privileges are stored in the server. In the main window, click  **User** or  **Role** to open the user/role object list.

MySQL / MariaDB User & Role Management

User Designer

General Properties

User Name

Define a name for the user account.

Host

Enter a host name or an IP address where the user connected from. % means any host.

Plugin

Select the account authentication plugin for the user.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Expire Password Policy

Select the password expiration policy for the user account.

Advanced Properties

Max queries per hour, Max updates per hour, Max connections per hour

Specify the maximum number of queries, updates, and connections that a user can perform during any given one-hour period. 0 means no limit.

Max user connections

Specify the maximum number of simultaneous connections that a user can make.

Use OLD_PASSWORD encryption

Use the OLD_PASSWORD() function to generate a hash value for storing user password.

SSL Type

Specify the SSL/TLS-related options for the user account.

ANY	Require SSL encryption when the user connects.
SPECIFIED	Require a valid certificate when the user connects. Provide Certificate Issuer , Certificate Subject , or SSL Cipher .
X509	Require a valid certificate when the user connects.

Member Of

Note: Roles are available for MySQL 8.0 or later or MariaDB 10.0.5 or later.

In the grid, check the **Granted** or **Default** option against the role listed in **Name** to assign this user to be a member of the selected role.

Server Privileges

In the grid, check the **Granted** option against the server privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Privileges

To edit specific object privileges for the user, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **State** option against the privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Role Designer

Note: Roles are available for MySQL 8.0 or later or MariaDB 10.0.5 or later.

General Properties

Role Name

Define a name for the role.

Member Of

In the grid, check the **Granted** option against the role listed in **Name** to assign this role to be a member of the selected role.

Members

In the grid, check the **Granted** option against the role/user listed in **Name** to assign the selected role/user to be a member of this role.

Server Privileges

In the grid, check the **Granted** option against the server privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Privileges

To edit specific object privileges for the role, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **State** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Oracle User & Role Management

User Designer

General Properties

User Name

Define a name for the user.

Authentication

Select the authentication method.

PASSWORD	Create a user. Specify a Password and re-type it in Confirm Password . Check the Expire Password option to force the user to change the password on the first attempted login.
EXTERNAL	Create a user authorised by an external service. Enter the certificate distinguished name or the Kerberos principal name in External Name .
GLOBAL	Create a user authorised by the enterprise directory service. Enter the X.509 name at the enterprise directory service that identifies the user in X.500 Name .

Default Table Space

Choose the default tablespace for objects that the user creates.

Temporary Table Space

Choose the tablespace or tablespace group for the user's temporary segments.

Profile

Choose the profile that assign to the user.

Lock Account

Lock the user's account and disable access.

Member Of

In the grid, check the **Granted**, **Admin Option** or **As Default** option against the role listed in **Role Name** to assign this user to be a member of the selected role.

Quotas

In the grid, specify the maximum amount of space that the user can allocate in the tablespaces. Enter the **Quota** and choose the **Unit**. **Unlimited** lets the user allocate space in the tablespace without bound. Multiple tablespaces can be set.

Server Privileges

In the grid, check the **Granted** or **Admin Option** option against the server privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

Privileges

To edit specific object privileges for the user, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** or **Grant Option** option against the privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

Role Designer

General Properties

Role Name

Define a name for the role.

Authentication

Select the authentication method.

PASSWORD	Create a role. Specify a Password and re-type it in Confirm Password .
EXTERNAL	Create a role authorised by an external service.
GLOBAL	Create a role authorised by the enterprise directory service.
NOT IDENTIFIED	Create a role without a password.

Member Of

In the grid, check the **Granted** or **Admin Option** option against the role listed in **Role Name** to assign this role to be a member of the selected role.

Members

In the grid, check the **Granted** or **Admin Option** option against the user listed in **Member** to assign the selected user to be a member of this role.

Server Privileges

In the grid, check the **Granted** or **Admin Option** option against the server privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

Privileges

To edit specific object privileges for the role, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Maintain User

Navicat provides a complete solution for maintaining Oracle users.

1. In the main window, select users in the Objects tab.
2. Right-click the selected users.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.

Option	Description
--------	-------------

Expire Password	Set the password of the user account to expire.
Lock Account	Lock the user account and disable access.
Unlock Account	Unlock the user account and enable access.

PostgreSQL User, Group & Role Management

User Designer

Note: Users are available for PostgreSQL 8.0 or below.

General Properties

User Name

Define a name for the user.

User ID

Specify an ID for the user.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Password Encryption

Choose whether the password is stored ENCRYPTED or UNENCRYPTED in the system catalogs.

Expiry Date

Set a datetime that the user's password will expire. If this option is omitted, the password will be valid for all time.

Superuser

Check this option to determine the user is a superuser.

Can create database

Check this option to allow the user to create databases.

Member Of

In the grid, check the **Granted** option against the group listed in **Group Name** to assign this user to be a member of the selected group.

Privileges

To edit specific object privileges for the user, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** or **Grant Option** option against the privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

Group Designer

Note: Groups are available for PostgreSQL 8.0 or below.

General Properties

Group Name

Define a name for the group.

Group ID

Specify an ID for the group.

Members

In the grid, check the **Granted** option against the user listed in **Member** to assign the selected user to be a member of this group.

Privileges

To edit specific object privileges for the group, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** option against the privilege listed in **Privilege** to assign this group to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Role Designer

Note: Roles are available for PostgreSQL 8.1 or later.

General Properties

Role Name

Define a name for the role.

Role ID

Specify an ID for the role.

Can login

Check this option to allow the role to log in.

Password

Specify a login password for the role.

Confirm Password

Re-type the login password.

Password Encryption

Choose whether the password is stored ENCRYPTED or UNENCRYPTED in the system catalogs.

Connection Limit

Specify how many concurrent connections the role can make. -1 means no limit.

Expiry Date

Set a datetime that the role's password will expire. If this option is omitted, the password will be valid for all time.

Superuser

Check this option to determine the role is a superuser.

Can create database

Check this option to allow the role to create databases.

Can create role

Check this option to allow the role to create roles.

Inherit privileges

Check this option to determine the role inherits the privileges of roles it is a member of.

Can update system catalog

Check this option to allow the role to update system catalog.

Can replicate

Check this option to allow the role to initiate streaming replication or put the system in and out of backup mode.

Can bypass RLS

Check this option to allow the role to bypasses every row-level security (RLS) policy.

Member Of

In the grid, check the **Granted** or **Admin Option** option against the role listed in **Role Name** to assign this role to be a member of the selected role.

Members

In the grid, check the **Granted** or **Admin Option** option against the role listed in **Member** to assign the selected role to be a member of this role.

Privileges

To edit specific object privileges for the role, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** or **Grant Option** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

SQL Server Login, Role & user Management

Login Designer

Note: The following options and tabs depend on the server version and the authentication type.

General Properties

Login Name

Define a name for the login.

Authentication Type

Select the authentication type of the login.

Password

Specify a password for the login.

Confirm Password

Re-type the login password.

Specify Old Password

Check this option to enter the old password used by this account when editing the login.

Enforce Password Policy

Check this option to force password to follow password policy of SQL Server.

Enforce Password Expiration

Check this option to force password to have expiry date.

User Must Change Password at Next Login

Check this option to force user to change password every time when login.

Default Database

Select the default database when login.

Default Language

Select the default display language when login.

Certificate Name

Select the certificate to be used for the login.

Asymmetric Key Name

Select the asymmetric key to be used for the login.

Enabled

Check this option to enable the login.

Credential

Select the credentials to be mapped to the login.

Roles

In the list, assign this server login to be a member of the selected server role.

User Mapping

In the grid, check the **Database** and enter the **User** and **Default Schema** to create user for login the database and specify the first schema will be searched by the server.

Server Permissions

In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the server permissions listed in **Permission** to assign this login to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Endpoint Permissions

In the grid, check the permissions against the endpoint listed in **Endpoint** to assign this login to have that endpoint permission. Click the checkbox twice to grant the permission with Grant Option. Click the checkbox three times to deny the permission.

Login Permissions

In the grid, check the permissions against the endpoint listed in **Login** to assign this login to have that login permission. Click the checkbox twice to grant the permission with Grant Option. Click the checkbox three times to deny the permission.

Server Role Designer

Note: Azure SQL Database does not support Server Role.

In the **Members** tab, assign the selected login to be a member of this server role.

Database User Designer

Note: The following options and tabs depend on the server version and the user type.

General Properties

User Name

Define a name for the database user.

Authentication

Select the security type for database user.

Login Name

Assign a SQL Server login that the database user uses.

Default Schema

Select the default schema that will own objects created by the database user.

Certificate Name

Select the certificate to be used for the database user.

Asymmetric Key Name

Select the asymmetric key to be used for the database user.

Roles

In the list, assign this database user to be a member of the selected database role.

Owned Schemas

In the list, check the schemas that are owned by the database user.

Database Permissions

In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the database permissions listed in **Permission** to assign this database user to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Object Permissions

To edit specific object permissions for the database user, click  **Add Permission** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the permission listed in **Privilege** to assign this database user to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Database Role Designer

Note: The following options and tabs depend on the server version.

General Properties

Role Name

Define a name for the database role.

Owner

Assign the owner for the database role.

Member Of

In the list, assign this database role to be a member of the selected database roles.

Members

In the list, assign the selected database users and roles to be a member of this database role.

Owned Schemas

In the list, check the schemas that are owned by the database role.

Database Permissions

In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the database permissions listed in **Permission** to assign this database role to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Object Permissions

To edit specific object permissions for the database role, click  **Add Permission** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the permission listed in **Privilege** to assign this database role to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Application Role Designer

Note: Azure SQL Database does not support Application Role. The following options and tabs depend on the server version.

General Properties

Role Name

Define a name for the application role.

Default Schema

Select the default schema that will own objects created by the application role.

Password

Specify a password for the application role.

Confirm Password

Re-type the password.


Owned Schemas

In the list, check the schemas that are owned by the application role.

Database Permissions

In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the database permissions listed in **Permission** to assign this application role to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Object Permissions

To edit specific object permissions for the application role, click  **Add Permission** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant**, **With Grant Option** or **Deny** option against the permission listed in **Privilege** to assign this application role to have that permission. To grant, deny or revoke all permissions, right-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

SQLite User Management

Note: By default, a SQLite database does not require user authentication (no-authentication-required database). After you created a user, the database will be marked as requiring authentication (authentication- required database). Then, user need to provide username and password when connecting to the database file.

General Properties

User Name

Define a name for the user account.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Administrator

Check this option to give the admin privilege to the user.

MongoDB User & Role Management

User Designer

General Properties

User Name

Define a name for the user.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Password Digestor

Indicate whether the server or the client digests the password.

Mechanisms

Specify the SCRAM mechanisms for creating SCRAM user credentials.

Custom Data

In this tab, you can enter any information associated with this user.


Built-In Roles

In the list, assign this user to be a member of the selected built-in role.

User-Defined Roles

In the list, assign this user to be a member of the selected user-defined role.

Authentication Restrictions

To edit specific authentication restrictions that the server enforces on the user, click  **Add Restriction.**

Client Source

Specify a list of IP addresses or CIDR ranges to restrict the client's IP address.

Server Address

Specify a list of IP addresses or CIDR ranges to which the client can connect.

Role Designer

General Properties

Role Name

Define a name for the role.

Built-In Roles

In the list, assign this role to be a member of the selected built-in role.

User-Defined Roles

In the list, assign this role to be a member of the selected user-defined role.


Members (Roles)

In the list, assign the selected role to be a member of this role.

Members (Users)

In the list, assign the selected user to be a member of this role.

Authentication Restrictions

To edit specific authentication restrictions that the server enforces on the role, click  **Add Restriction**.

Client Source

Specify a list of IP addresses or CIDR ranges to restrict the client's IP address.

Server Address

Specify a list of IP addresses or CIDR ranges to which the client can connect.

Privileges

To edit specific object privileges for the role, click  **Add Privilege** to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the objects that you want to grant the privileges on.
3. In the grid, check the **State** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, right-click on the grid and select **Grant All** or **Revoke All**.

Redis User Management

You can define users in Redis Access Control Lists (ACLs) to protect access to your data. Navicat provides a graphical interface for you to create, edit and delete users.

Note: Users are available for Redis 6 or later.

General Properties

User Name

Define a name for the user account.

Can login

Enable the user account.


Require Password

Require the user to log in with a password.


Add Password

Add a password or a SHA-256 hash value to the list of valid passwords for the user.


Privileges

You can create new privilege groups (selectors) to add multiple sets of rules to the user. New privilege groups are evaluated after the main privilege group, and are evaluated according to the order they are defined. Click  **Add Privilege Group / Add Privilege Groups with Batch.**


Commands

To allow and disallow commands, click  **Add Command / Add Commands with Batch.** @all implies all the commands, both those currently present in the server, and those that will be loaded via modules in the future.

Keys

To allow and disallow certain keys and key permissions, click  **Add Key / Add Keys with Batch.** You can enable **Grant privilege of all keys** to allow the user to access all keys.


Channels


To allow and disallow Pub/Sub channels, click  **Add Channel / Add Channels with Batch.** You can enable **Grant privilege of all channels** to allow the user to access all Pub/Sub channels.

Privilege Manager

Besides setting privileges in each user, **Privilege Manager** provides another view on privileges in a connection and its database objects.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server, MariaDB and MongoDB.

To add privileges, click  **Privilege Manager** from the user object toolbar and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Choose the object and click  **Add Privilege** to open the window.
3. Check the user on the left pane.
4. In the grid, check the relevant options against the privileges listed in **Privilege** to assign the selected user to have that object privilege.

Chapter 17 - Other Advanced Tools

Server Monitor (Available only in Non-Essentials Edition)

Navicat provides **Server Monitor** to view properties of selected servers. Choose **Tools -> Server Monitor** and choose the preferred server type from the menu bar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server, MariaDB, MongoDB and Redis.

Process List

This tab displays a list of processes from all selected servers. The process list provides the following detailed information. It depends on the database type you are chosen.

If you want to take action on auto-refreshing the process list in assigned seconds, choose **View -> Set Auto Refresh Time** and enter a refresh time value. To enable or disable the Auto Refresh feature, choose **View -> Auto Refresh**.

Note: Effect will take once you assign the value.


To set a selected process always show on the top of the grid, right-click and select **On Top**. To cancel this setting, choose **Cancel On Top**.

To stop a selected process, click the  **End Process** button.

Variables

Note: Available only for MySQL, Oracle, PostgreSQL, MariaDB, MongoDB and Redis.

This tab displays a list of all server variables and their values.



You can edit MySQL, MariaDB, Oracle and Redis variable values here. Click  or press CTRL+ENTER to open an editor for editing.

Status

Note: Available only for MySQL, Oracle, PostgreSQL, MariaDB, MongoDB and Redis.

This tab displays a list of all server status and their values.





Schema Analysis (Available only in Non-Essentials Edition)

Schema Analysis is used for verifying your schemas, visualizing data distributions and identifying data outliers. To start, select a collection or a view in the Objects tab and click  **Analyze Schema**, or click  **Analyze** in the data viewer.

Note: Available only for MongoDB.

Hint: Schema Analysis Profiles (.nsatmongodb) are stored under the [Settings Location](#).


Toolbar

Option / Button	Description
 Filter	Filter the documents for analyzing.
 Projection	Include or exclude fields for analyzing.
Analyze:	Select the sample documents from the collection for analyzing.
 Analyze	Start analyzing the sample documents.
 Stop	Stop analyzing the sample documents.

Results

After the analysis has completed, you will see the schema analysis results. The results visually display information about the type and data distribution of all fields.

If a field has multiple field types, you can click the field type bar on the left, and the chart will show the data distribution chart of that type.








Command Monitor (Available only in Non-Essentials Edition)

Command Monitor is a real-time command monitoring tool that allows you to monitor every command processed by the Redis server instantly. It can help you understand what is happening to the database. To open the monitor, right-click on the connection and select **Command Monitor**.

Note: Available only for Redis.

Note: Command Monitor may reduce the performance of the Redis server significantly.

The toolbar provides the following functions:

Button	Description
 Start	Start monitoring the Redis server.
 End	Stop monitoring the Redis server.
 Word Wrap	Break long words and wrap onto the next line.
 Export	Export the commands to a text file.
 Clear	Clear the commands.

Virtual Grouping (Available only in Non-Essentials Edition)

Virtual Group aims to provide a platform for logical grouping objects by categories, so that all objects are effectively preserved. It can be applied on Connection, Table, Collection, Data, View, Materialized View, Function, Index, Trigger, MapReduce, GridFS, Pub/Sub, Query, Backup, Automation, Model and Charts.

Hint: The vgroup.json file is saved under the [Profiles Location](#).

If you want to hide the group structure, choose **View -> Navigation Pane -> Flatten Connection** and choose **View -> Flatten Object List**.

Create a new group

1. In the main window, right-click on the Navigation pane or the Objects tab and select **New Group** or **Manage Group -> New Group**.
2. Enter a name for the new group.

Move an object to a group

1. In the main window, right-click an object and select **Manage Group -> Move To**.
2. Select an existing group.

Move an object to the top-level


1. In the main window, right-click an object and select **Manage Group -> Exclude From Group**.

Hint: You can also use the drag and drop method to move objects.

Connection Colorings

Navicat provides highlighting connections by colors for identifying connections and their database objects. It lets you immediately know which connection you're connected to when you working on database objects. The highlighted color displays in the Navigation pane and the menu bar or the tab of its object window.

To highlight a connection, right-click a connection in the Navigation pane and select **Color**.



Find in Database/Schema (Available only in Non-Essentials Edition)

Navicat provides a **Find in Database/Schema** feature offers searching table and view records or object structures within a database and/or schema. To open the Find in Database/Schema window, choose **Tools -> Find in Database/Schema** from the menu bar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

1. Select a target **Connection**, **Database** and/or **Schema**.
2. Enter the search string in **Find what**.
3. Choose to find Data or Structure in the **Look in** drop-down list.
4. Choose the **Search Mode**: Contains, Whole Word, Prefix or Regular Expression.
5. Check the **Case Insensitive** box to disable case sensitive search if necessary.
6. When finding Structure, you can choose to search different objects: Tables, Collections, Views, Functions, Queries, Indexes, Triggers, Events and/or Materialized Views.
7. Click the **Find** button and then double-click an object in the **Find Results** list to view the record or the structure.

Print Structure (Available only in Non-Essentials Edition)

Navicat allows you to view and print database, schema and table structures, including table names, field names, field types and other field properties. In the main window, right-click a database, a schema or tables and select **Print**

Database or **Print Schema** or **Print Tables**. A structure report window will pop up. You can send the structures to printer or print it to other file formats, such as PDF, HTML.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB.

Console

Console allows you to use a command-line interface to work with your server. In other words, it provides interactive text-based screen for you to query input and result output from databases. To open the Console window, open a connection and choose **Tools** -> **Console** from the menu bar or press F6.

Hint: You are allowed to open multiple console windows which each represents a different connection.

Oracle

For Oracle servers, you must have **SQL*Plus** executable for this feature to work. By default, Navicat will look for SQL*Plus under client folder (e.g. ORACLE_HOME\bin). However, if Navicat cannot locate SQL*Plus under the [SQL*Plus default path](#), you are prompted to locate the executable.

Note: SQL*Plus does not support Unicode.

MongoDB

For MongoDB servers, you must have **Mongo Shell** executable for this feature to work. If Navicat cannot locate Mongo Shell under the [Mongo Shell default path](#), you are prompted to locate the executable.

Redis

For Redis servers, code completion and syntax highlighting are supported. It lets you type Redis commands smoothly.

Favorites (Available only in Non-Essentials Edition)

Favorites are links to database objects that you visit frequently. By adding a path to your favorites list, you can go to that database objects with a single click, instead of having to navigate the connection, database and/or schema in the Navigation pane.

Add a link to Favorites

1. Open an object, e.g. table.
2. Choose **File** / **Favorites** -> **Add to Favorites** or press SHIFT+CTRL+#. If the object is opened in tabbed window, you can right-click the tab and select **Add to Favorites**.
3. Enter **Favorite Name** and select **Favorite ID** if the **Add to Favorites** window pops up.

Open an object from Favorites

1. Choose **Favorites** -> **favorite_name** or press CTRL+#.

Remove links from Favorites


- Choose **Favorites -> Clear Favorites -> favorite_name** to remove a link.
- Choose **Favorites -> Clear Favorites -> Clear All** to remove all links from the favorites list.

Note: # represents 1, 2, 3, 4, 5, 6, 7, 8 or 9.

Dark Theme

In Dark Theme, Navicat uses a darker color palette for all windows, views, menus, and controls. It works on all supported version of Windows.


To change your theme, choose **Tools -> Options -> General**. Then, select **Dark**.



Search Filter

Navicat provides search filters for searching your objects in the Navigation pane, the Objects tab, the Model Designer window and other tree structures.

In the Navigation pane or other tree structures, click on the tree to focus and enter a search string directly. If connections have opened in the Navigation pane, the filter will also apply to their database objects.

In the Objects tab, click  and enter a search string in the **Search** text box.

In the Model Designer window, simply enter a search string in the **Search** text box.

You can remove the filter by deleting the search string.

Chapter 18 - Configurations

Options Settings

Navicat provides several options for customizing its user interface and performance.

To open the Options window, choose **Tools -> Options** from the menu bar.

General

General

Theme

Choose to use the theme of your Windows OS or a Dark theme.

Hint: Restart Navicat to take effect.

Allow opening multiple forms for same object

Check this option to allow opening multiple instances of an object.

Show objects under schema in navigation pane

Display database objects using the tree structure in the Navigation pane. To expand a node, simply double-click it.

Hint: Reopen the database/schema to take effect.

Show objects under table in navigation pane

Display table elements (e.g. fields, indexes, foreign keys) using the tree structure in the Navigation pane. To expand a node, simply the arrow to the left of the table name.

Hint: Reopen the database/schema to take effect.

Show toolbar caption

Show text on toolbar buttons in sub-windows. Otherwise, only buttons will be presented.

Hint: Restart Navicat to take effect.



Show function wizard

Display the function wizard (MySQL, Oracle, PostgreSQL, SQL Server or MariaDB) when you create a new function/procedure.

Ask to save new queries/profiles before closing

With this option is on, Navicat will prompt you to save new queries or profiles every time when you quit the relevant sub-window.

Check for updates on startup

Check this option to allow Navicat checks for new version when it starts.

Use safe confirm dialog (Main Window)

With this option is on, Navicat will prompt a double confirmation dialog for safe deletion when deleting objects in the main window.

Usage Data

Share Usage Data

Check this option to let your device sends us information about how you use Navicat to help us improve it. You can view the information being shared by clicking the **Usage Data** button.

Tabs

Open new tab in

Set new pop-up windows to open as:

Option	Description
Main Window	Open a new tab in the main window.
Last Tab Window	Open a new tab in the last opened window (including the main window).
Last Tab Window (Except Main Window)	Open a new tab in the last opened window, or a new window if there isn't any opened windows.
New Window	Open a new window.

On Startup

Control what tabs appear when you launch Navicat:

Option	Description
Open Objects tab only	Open the Objects tab only, and no other tabs.
Continue where you left off	Open the Objects tab, and reopen the same tabs you were opened when you last quit Navicat.
Open a specific tab or set of tabs	Open the Objects tab, and open the tabs you choose in Set Tabs .

Hint: Restart Navicat to take effect.

Code Completion (Available only in Non-Essentials Edition)

Use code completion

When you type the . (dot) symbol or a character, the editor will offer you a pop-up list that showing some suggestions for the code completion.

Auto update code completion info

With this option is on, Navicat will get the latest database information for code completion from your server automatically when you open the database/schema. Otherwise, you will need to update it manually in the Query window.

Auto select first suggestion

Select the first item automatically when the suggestion list pops up. Therefore, pressing ENTER or TAB will insert the selected item. Otherwise, you need to use arrow keys to select the suggestion item.

Clear Code Completion Info

Delete the information for code completion feature that stored on your device.

Editor

General

Show line number

Display line numbers at the left side of the editor for easily reference.

Use code folding

Code folding allows codes to collapse as a block and only the first line displayed in the editor.

Use brace highlighting

Highlight the pair of braces when your cursor moves to either one brace for easily reference.

Use syntax highlighting

Syntax highlight helps viewing codes clearly. Codes are highlighted in the editor with different colors and fonts according to the categories they belong to. This feature can be limited by setting the maximum file size (e.g. 10) in **Disable if file size is larger than (MB)** to increase performance.

Use word wrap

Enable the word wrap mode in the editor.

Tab Width

Enter the number of characters that a tab occupies, e.g. 5.

Font and Colors

Editor Font

Define the font and its size used by editors.

Colors

Format your SQL queries in SQL Editor with colored syntax highlighting for your SQL statements to improve readability. Set font colors to mark out different text fragments: Common, Keyword, String, Number, Comment and Background. Click on the color boxes and choose your desired color from the Color-Selection dialog window.

Records


Records



Limit records ☐ **records per page**

Check this option if you want to limit the number of records showed on each page in the grid/foreign key data selection globally. Otherwise, all records will be displayed in one single page.

Note: To adjust the settings for particular table/collection, see [Data Viewer](#).

Auto Begin Transaction

Check this option to start a new transaction automatically when changing records in the table/collection. Otherwise, auto commit is on and you need click the  **Begin Transaction** button in Data Viewer to start a transaction manually.

When starting a transaction in Data Viewer, you can use the  **Commit** or  **Rollback** buttons to commit or rollback the changes. See [Data Viewer](#).

Grid

Grid Font

Define the font and its size used by grid in Data Viewer.

Display Format

Data of types date, time and datetime can be formatted when displayed on data grids. Type the format here to change the format. If the formats are left blank, default format will be used. Default formats will be the system datetime formats.

Display Format

Date:

dd-mm-yyyy

Time:

hh:mm:ss

DateTime:

dd-mm-yyyy hh:mm:ss

Example:

6/29/2022 3:15:49 PM

Output:

29-06-2022 15:15:49

The following table shows specifiers you can use to create user-defined datetime formats.

Date Time Fields

Specifier	Description
c	Display the date using the format given by the system global variable, followed by the time using the format given by the system global variable. The time is not displayed if the date-time value indicates midnight precisely.
d	Display the day as a number without a leading zero (1-31).
dd	Display the day as a number with a leading zero (01-31).
ddd	Display the day as an abbreviation (Sun-Sat).
dddd	Display the day as a full name (Sunday-Saturday).
dddddd	Display the date using the format given by the system global variable.
ddddddd	Display the date using the format given by the system global variable.
m	Display the month as a number without a leading zero (1-12). If the m specifier immediately follows an h or hh specifier, the minute rather than the month is displayed.
mm	Display the month as a number with a leading zero (01-12). If the mm specifier immediately follows an h or hh specifier, the minute rather than the month is displayed.
mmm	Display the month as an abbreviation (Jan-Dec) using the strings given by the system global variable.
mmmm	Display the month as a full name (January-December) using the strings given by the system global variable.
yy	Display the year as a two-digit number (00-99).
yyyy	Display the year as a four-digit number (0000-9999).
h	Display the hour without a leading zero (0-23).
hh	Display the hour with a leading zero (00-23).
n	Display the minute without a leading zero (0-59).
nn	Display the minute with a leading zero (00-59).
s	Display the second without a leading zero (0-59).
ss	Display the second with a leading zero (00-59).
t	Display the time using the format given by the system global variable.
tt	Display the time using the format given by the system global variable.
am/pm	Use the 12-hour clock for the preceding h or hh specifier, and display 'am' for any hour before noon, and 'pm' for any hour after noon. The am/pm specifier

	can use lower, upper, or mixed case, and the result is displayed accordingly.
a/p	Use the 12-hour clock for the preceding h or hh specifier, and display 'a' for any hour before noon, and 'p' for any hour after noon. The a/p specifier can use lower, upper, or mixed case, and the result is displayed accordingly.
ampm	Use the 12-hour clock for the preceding h or hh specifier, and display the contents of the system global variable for any hour before noon, and the contents of the system global variable for any hour after noon.
/	Date separator. In some locales, other characters may be used to represent the date separator.
:	Time separator. In some locales, other characters may be used to represent the time separator.
'xx'/'"xx"	Characters enclosed in single or double quotes are displayed as-is, with no formatting changes.

Format specifiers may be written in uppercase or lowercase letters; both produce the same result.

Show Thousands Separator

Check this option to show the thousands separator for numeric data.

Use system locale decimal & thousands separator

Check this option to use the system separators that are defined in the regional settings in OS. Otherwise, use dot (.) as the decimal separator and comma (,) as the thousands separator.

Auto Recovery

Query / Model / Charts

Save automatically after modifications in queries, models or workspaces by defining the **Auto Save Interval (seconds)** (e.g. 30).

File Locations

Logs Location

Navicat provides number of [log files](#) to keep track on the actions have been performed in Navicat and they are located in the Logs Location path.

Profiles Location

By default, most of Navicat files and profiles are stored in [Settings Location](#). However, some files and profiles are located in the Profiles Location paths.

File in Profiles Location	Server Type	File Extension
Automation	MySQL	.nbatmysql

	Oracle	.nbatora
	PostgreSQL	.nbatpgsql
	SQLite	.nbatsqlite
	SQL Server	.nbatmssql
	MariaDB	.nbatmariadb
	MongoDB	.nbatmongodb
	Redis	.nbatredis
	Premium (Cross Server)	.nbatpremium
Charts (Workspace)	All	.ncharts
Code Snippet	All	.nsnippet
Data Generation	MySQL	.ndgrmysql
	Oracle	.ndgrora
	PostgreSQL	.ndgrpgsql
	SQLite	.ndgrsqlite
	SQL Server	.ndgrmssql
	MariaDB	.ndgrmariadb
	MongoDB	.ndgrmogodb
Data Synchronization	MySQL	.ndsymysql
	Oracle	.ndsyora
	PostgreSQL	.ndsypgsql
	SQLite	.ndsysqlite
	SQL Server	.ndsymssql
	MariaDB	.ndsymariadb
	MongoDB	.ndsymongodb
Data Transfer	MySQL	.ndtfmysql
	Oracle	.ndtfora
	PostgreSQL	.ndtfpgsql
	SQLite	.ndtfsqlite
	SQL Server	.ndtfmssql
	MariaDB	.ndtfmariadb
	MongoDB	.ndtfmongodb
	Premium (Cross Server)	.ndtfpremium
Model	MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB	.ndm2, .ndml2, .ndmc2
MongoDump	MongoDB	.nmdpmongo
MongoExport	MongoDB	.nmepmongo
MongoImport	MongoDB	.nmipmongo
MongoRestore	MongoDB	.nmrsmongo
Structure Synchronization	MySQL	.nssymysql
	Oracle	.nssyora

	PostgreSQL	.nssypgsql
	SQL Server	.nssymssql
	MariaDB	.nssymariadb
Virtual Grouping	All	vgroup.json - stores how the objects are categorized.

Export Wizard

Set the default export directory when exporting data.

Connectivity

General

Verify server certificate against CA

Enable this option to verify that the server certificate against the list of trusted CA.

Proxy

Enable the **Use proxy** option to configure Navicat to use proxy in order to make its network connections.

Proxy Type

Specify the type of your proxy server: HTTP or SOCKS5.

Host

The host name of your proxy server.

Port

The port number of your proxy server.

User Name / Password

If your proxy server requires authentication, you can enter a username and a password.

Connectivity Diagnosis

Click **Test Connectivity** to test the network connectivity between the web service and your machine.

Environment

Executables

SQL*Plus (Available only for Oracle)

Specify the location for SQL*Plus used in the [console](#) of Oracle connections. SQL*Plus is included in Oracle Client / Oracle Instant Client.

Mongo Shell Path (Available only for MongoDB)

Specify the location for Mongo Shell used in the [console](#) of MongoDB connections.

MongoDump Executable Path (Available only for MongoDB)

Specify the location of the mongodump executable that used for [MongoDump](#).

MongoRestore Executable Path (Available only for MongoDB)

Specify the location of the mongorestore executable that used for [MongoRestore](#).

MongoImport Executable Path (Available only for MongoDB)

Specify the location of the mongoimport executable that used for [MongoImport](#).

MongoExport Executable Path (Available only for MongoDB)

Specify the location of the mongoexport executable that used for [MongoExport](#).

External Editor

Choose the file path of an external editor for opening queries.

OCI Environment (Available only for Oracle)

OCI library (oci.dll)

Specify the location for the OCI library (oci.dll) for Oracle connection. By default, it is set to the bundled one in Navicat installation folder.

Hint: Restart Navicat to take effect.

Oracle Instant Client is the simplest way to deploy a full Oracle Client application built with OCI, OCCI, JDBC-OCI, or ODBC drivers. It provides the necessary Oracle Client libraries in a small set of files. You can also download Oracle Instant Client through -

[Oracle Instant Client](#)

Download the appropriate Instant Client packages for your platform and the CPU. All installations REQUIRE the Basic or Basic Lite package. Unzip the packages and set the path points to it.

Advanced

Enable diagnostic logging

Generate a log file in [Logs Location](#) to assist with tracking down any problems in Navicat.

Hint: Restart Navicat to take effect.

Allow multiple Navicat instances

Check this option to allow opening multiple instances of Navicat. Uncheck this item means that clicking on the Navicat shortcut will re-activate the running instance of Navicat and not launch a new copy.

Register on "Open with" List

Register Navicat program to the "Open with" list in Windows.

Register Navicat URI Protocol

Register Navicat URI protocol in Windows. When clicking a Navicat URI link, Navicat opens and adds the corresponding Navicat On-Prem Server using the parameters in the URI.

Chapter 19 - Hot Keys

Navicat Hot Keys

Common

Keys	Action
CTRL+SHIFT+# (# represents 1 to 9)	Add to Favorites
F8	Navicat Main Window / Objects Tab
CTRL+TAB or SHIFT+CTRL+TAB	Next Window / Tab
CTRL+Q	New Query
F1	Help

Navicat Main Window

Keys	Action
CTRL+# (# represents 1 to 9)	Open Favorites Link
F6	Console
CTRL+L	History Log
F12	Show Only Active Objects
CTRL+N	New Object
CTRL+SHIFT+F	Find in Database/Schema

ER Diagram View

Keys	Action
F5	Refresh
ESC	Select
H	Move Diagram
R	New Foreign Key
DELETE	Delete Selected Foreign Key
CTRL+= or CTRL+Mousewheel Up	Zoom In
CTRL+- or CTRL+Mousewheel Down	Zoom Out
CTRL+0	Reset Zoom

Table / Collection Designer

Keys	Action
CTRL+O	Open Table / Collection
CTRL+F	Find Field
F3	Find Next Field
SHIFT+F3	Find Previous Field

Data Viewer

Keys	Action
CTRL+D	Design Object (Table, Collection, View, Materialized View)
CTRL+Q	Query Object (Table, Collection, View, Materialized View)
CTRL+F	Find Text
F3	Find Next Text
CTRL+G	Go to Row
CTRL+LEFT ARROW	Move to First Column of Current Record
CTRL+RIGHT ARROW	Move to Last Column of Current Record
CTRL+HOME	Move to First Row of Current Column
CTRL+END	Move to Last Row of Current Column
CTRL+PAGE UP or CTRL+UP ARROW	Move to First Row of Current Page
CTRL+PAGE DOWN or CTRL+DOWN ARROW	Move to Last Row of Current Page
CTRL+R	Apply Filter / Apply Sort
SHIFT+ARROW	Select Cells
CTRL+ENTER	Edit Data with Opening Editor
INSERT or CTRL+N	Add Record
CTRL+DELETE	Delete Records
CTRL+S	Apply Record Changes
ESC	Discard Record Changes
CTRL+T	Stop Loading Data

View / Materialized View Designer

Keys	Action
CTRL+O	Import SQL
CTRL+E	Switch to Definition
CTRL+R	Preview
ALT1	Switch to Result Tab

Query Designer

Keys	Action
CTRL+O	Open External File
CTRL+E	Select Current Statement
CTRL+R	Run / Run Selected
CTRL+SHIFT+R	Run Current Statement
CTRL+T	Stop
ALT+# (# represents 0 to 9)	Switch to Result Tab

Query Editor

Keys	Action
------	--------

CTRL+SHIFT+V	Paste from Clipboard Stack
CTRL+/	Comment / Uncomment Line
CTRL+F	Find Text
F3	Find Next Text
CTRL+=	Zoom In
CTRL+-	Zoom Out
CTRL+0	Reset Zoom

Query Builder

Keys	Action
CTRL+=	Zoom In
CTRL+-	Zoom Out
CTRL+0	Reset Zoom

Debugger

Keys	Action
F9	Run
F10	Step Over
F11	Step In
SHIFT+F11	Step Out

Model

Keys	Action
CTRL+D	New Diagram in Model
CTRL+P	Print Diagram
ESC	Select
H	Move Diagram
T	New Table/Entity
V	New View
R	New Foreign Key/Relation
A	New Label
N	New Note
I	New Image
L	New Layer
CTRL+B	Bold Selected Table, Entity, View, Foreign Key, Relation or Shape
CTRL+= or CTRL+Mousewheel Up	Zoom In
CTRL+- or CTRL+Mousewheel Down	Zoom Out
CTRL+0	Reset Zoom

Charts

Keys	Action
CTRL+D	Design Object
F5	Refresh Data
F11	Present Dashboard
CTRL+P	Print Dashboard


Chapter 20 - Trace Logs

Log Files


Navicat provides number of log files to keep track on the actions have been performed in Navicat and they are located in the **logs** directory, e.g. C:\Users\Guest\Documents\Navicat\Premium\logs\. You are allowed to change the log files location under [Options](#).

File	Description
history.log	Store the statements or scripts of all operations executed over databases and database objects in Navicat. To open the history.log file in the History Log Viewer , choose Tools -> History Log or press CTRL+L. Note: This log will be overwritten while Navicat is being restarted.
cmdline.log	Store information for Navicat command line process and all operations while running batch jobs.
LogImport.txt	Record detailed information on every error (indicating success or failure) that occurred during the import process. Note: This log will be overwritten on each import.
navicat.log	Store information to assist with tracking down any problems in Navicat. You can enable this log in Options . Note: This log will be overwritten while Navicat is being restarted.

History Log Viewer

History Log Viewer shows the statements or scripts that are executed or executing in Navicat. If you just want to display error messages, click  **Show Error Only**. You can also change the information shown by choosing from the **View** menu -

- Show Date
- Show Time
- Show Server Name
- Show Session ID
- Show Connection Type
- Show Execute Time

Note: When you click  **Pause**, any actions that you do while history is paused will show after resuming.

History Log

File Edit View Window Help

Clear Word Wrap Show Errors Only Pause

4343

4344 [2022-06-29 15:12:27.856][Production Server 02][000140][MYSQL]

4345 SHOW TABLE STATUS

4346 Time: 0.001s

4347

4348 [2022-06-29 15:12:31.404][Production Server 02][000140][MYSQL]

4349 SELECT * FROM `hr`.`employees` LIMIT 0,1000

4350 Time: 0.006s

4351

4352 [2022-06-29 15:12:31.411][Production Server 02][000140][MYSQL]

4353 SHOW TABLE STATUS LIKE 'employees'

4354 Time: 0.000s

4355

4356 [2022-06-29 15:12:31.414][Production Server 02][000142][MYSQL]

4357 SHOW COLUMNS FROM `hr`.`employees`

4358 Time: 0.015s

4359

4360 [2022-06-29 15:12:31.43][Production Server 02][000141][MYSQL]

4361 SHOW CREATE TABLE `hr`.`employees`

4362 Time: 0.000s

4363

4364 [2022-06-29 15:12:31.431][Production Server 02][000142][MYSQL]

4365 SHOW INDEX FROM `employees`

4366 Time: 0.001s

4367

4368 [2022-06-29 15:12:31.434][Production Server 02][000140][MYSQL]

4369 SHOW CREATE TABLE `employees`

Last Refresh Time: 15:16:52